

**Specification of**  
**RobotFramework AIO**  
**v. 0.5.1**  
**at Bosch**

Implemented by:

*Thomas Pollerspöck*

*Nguyen Huynh Tri Cuong*

*Tran Duy Ngoan*

*Mai Dinh Nam Son*

*Tran Hoang Nguyen*

*Holger Queckenstedt*

**07/2022**

# Contents

<b>1</b>	<b>Apertis Pro</b>	<b>1</b>
1.1	How to use DLT . . . . .	1
1.1.1	dlt-daemon on Apertis . . . . .	1
1.1.2	Apertis Pro firewall configuration . . . . .	1
1.1.3	DLTSelfTestApp . . . . .	1
1.1.4	QConnectDLTLibrary . . . . .	2
<b>2</b>	<b>Code analysis</b>	<b>4</b>
<b>3</b>	<b>Library documentation</b>	<b>6</b>
3.1	GenPackageDoc . . . . .	8
3.2	PythonExtensionsCollection . . . . .	31
3.3	RobotframeworkExtensions . . . . .	63
3.4	JsonPreprocessor . . . . .	71
3.5	RobotFramework_Testsuites . . . . .	79
3.6	QConnectBase . . . . .	96
3.7	QConnectionDLTLibrary . . . . .	122
3.8	RobotResults2RQM . . . . .	136
3.9	RobotResults2DB . . . . .	154
3.10	TestResultWebApp . . . . .	172
3.11	TMLLog2RobotLog . . . . .	182

# Chapter 1

## Apertis Pro

### 1.1 How to use DLT

#### 1.1.1 dlt-daemon on Apertis

Verify that **dlt-daemon** has installed on Apertis Pro target or not.

```
systemctl status dlt-daemon
```

In case **dlt-daemon** is not available, follow below steps to install and start dlt-daemon service:

- Install **dlt-daemon** package

```
sudo apt install dlt-daemon
```

- Start **dlt-daemon** service

```
sudo systemctl start dlt-daemon
```

#### 1.1.2 Apertis Pro firewall configuration

In order to capture DLT log/trace from DLT client(**DLT Viewer**, **DLTConnector**), DLT client has to communicate with Apertis Pro (TCP/IP protocol) via port **3490** (as default).

So that, this connection should be allowed on Apertis Pro target.

Adopt settings of firewall at Apertis Pro:

- Add new rule to allow DLT service at port **3490** (as default)

Edit `/etc/iptables/rules.v4` file to add below line

```
...
# Accept dlt for development
-A INPUT -p tcp -m state --state NEW -m tcp --dport 3490 -j ACCEPT
...
```

- Restart the firewall with changed parameters

```
sudo systemctl restart iptables.service
```

#### 1.1.3 DLTSelfTestApp

**DLTSelfTestApp** is an application which will be run on the Apertis Pro target for testing the DLT connection between RobotFramework AIO and target.

This package is a part of RobotFramework AIO selftest helpers.

To install **DLTSelfTestApp**, download its debian package on Apertis Pro target then execute the below command.

```
sudo dpkg -i <path/to/dltselftestapp_1.0.0_amd64.deb>
```

**DLTSelfTestApp** application will be installed in `/opt/bosch/rob主w/dlt` directory and can be started with below command:

```
/opt/bosch/rob主/dlt/DLTSelfTestApp
```

Welcome log message `Welcome to RobotFramework AIO DLTSelfTestApp...` will be sent at application startup.

Then the ping log `ping message from RobotFramework AIO DLTSelfTestApp` every 5 seconds.

### DLT command injection:

To perform the DLT command injection, use below information:

- App ID: **RBFW**
- Context ID: **TEST**
- Service ID: **0x1000**
- Data as Textdata

DLT log reponse of **DLTSelfTestApp** will bases on injected command:

- `welcome` : DLT reponse as above welcome message.
- `exit` : DLT reponse as `Bye...` then **DLTSelfTestApp** will be terminated.
- Other commands: DLT reponse as combination of data and string.

e.g: `Data: 000000: 77 65 6c 63 6f 6d 65 31 32 31 32 00 xx xx xx xx welcome1212`

#### 1.1.4 QConnectDLTLibrary

**QConnectDLTLibrary** is part of RobotFramework AIO. It provides the ability for handling connection to Diagnostic Log and Trace(DLT) Module. The library support for getting trace message and sending trace command

Sample RobotFramework AIO testcase which are using **QConnectDLTLibrary** to test DLTSelfTestApp on Apertis Pro target:

- Header of a RobotFramework AIO testcase containing common settings ( `*** Settings ***` ) like the setups and teardowns, the definition of variables ( `*** Variables ***` ) and the definition of keywords ( `*** Keywords ***` ):

```
*** Settings ***
Documentation  This is selftest for DLT connection with DLTSelfTestApp
Library       QConnectionLibrary.ConnectionManager
Suite Setup   Open Connection
Suite Teardown Close Connection

*** Variables ***
${CONNECTION_NAME}  TEST_CONN_DLTSelfTestApp
${DLT_CONNECTION_CONFIG} =  SEPARATOR=
... {
...     "gen3flex@DLTSLIMWFH": {
...         "target_ip": "127.0.0.1",
...         "target_port": 4490,
...         "mode": 0,
...         "ecu": "ECU1",
...         "com_port": "COM1",
...         "baudrate": 115200,
...         "server_ip": "localhost",
...         "server_port": 1234
...     }
... }

*** Keywords ***
Close Connection
    disconnect  ${CONNECTION_NAME}
    Log to console    \nDLT connection has been closed!

Open Connection
```

```

    ${dlt_config} =      evaluate      json.loads('"'${DLT_CONNECTION_CONFIG}"')      json

connect                conn_name=${CONNECTION_NAME}
...                    conn_type=DLT
...                    conn_mode=dltconnector
...                    conn_conf=${dlt_config}

Log to console         \nDLT connection has been opened successfully!

```

- Sample RobotFramework AIO testcase to verify the ping message from DLTSelfTestApp

```

*** Test Cases ***
Match log/trace from DLTSelfTestApp
[Documentation]      Match log/trace from DLTSelfTestApp
[Tags]              DLTSelfTestApp
${res}=             verify      conn_name=${CONNECTION_NAME}
...                  search_pattern=(DLT:0x01.*RBFW.*)
...                  timeout=6    # DLTSelfTestApp pings a message every 5 seconds

# log to console     \n${res}[0]
# verify that reponse message should contain "Ping" keyword
Should Match Regexp  ${res}[0]    DLT:0x01.*RBFW.*Ping.*

```

- Sample RobotFramework AIO testcase to verify command injection with DLTSelfTestApp

```

Command injection with DLTSelfTestApp
[Documentation]      Get log/trace from DLTSelfTestApp
[Tags]              DLTSelfTestApp
${res}=             verify      conn_name=${CONNECTION_NAME}
...                  search_pattern=(DLT:0x01.*RBFW.*Welcome.*)
...                  send_cmd=DLT_CALL_SW_INJECTION_ECU ECU1 1000 RBFW TEST ↵
↵ 'welcome'

# log to console     \n${res}[0]

${res}=             verify      conn_name=${CONNECTION_NAME}
...                  search_pattern=(DLT:0x01.*RBFW.*other_cmd.*)
...                  send_cmd=DLT_CALL_SW_INJECTION_ECU ECU1 1000 RBFW TEST ↵
↵ 'other_cmd'

# log to console     \n${res}[0]

```

Please refer [QConnectDLTLibrary repository](#) for more details about usage and other example testcase for DLT connection.

## Chapter 2

# Code analysis

The RobotFramework AIO installation provides a static code analyser to detect potential errors and violations to coding conventions. The name of the analyser is **Robocop**.

Robocop is integrated in Visual Studio Code and is triggered automatically in case of

1. a file is opened in editor,
2. a file is changed and saved.

The outcome will look like this:

```

suite02.robot 3 X
robotframework-tutorial > 901_static_code_analysis > suite02.robot > ...
31 Test Case 0201
32     ...[Documentation]...Documentation of test case
33     ...Log...I am test '${TEST_NAME}' of suite '${SUITE_NAME}'...console=yes
34     ...# TODO: Add return value to keyword implementation; check return value here
35     ...test_keyword_1
36
37 Test Case 0201
38     ...[Documentation]...Documentation of test case
39     ...Log...I am test '${TEST_NAME}' of suite '${SUITE_NAME}'...console=yes
40
41
42
43

```

PROBLEMS 6 OUTPUT DEBUG CONSOLE TERMINAL Filter (e.g. text, \*\*/\*.ts, !\*\*/node\_modules/\*\*)

▼ suite02.robot robotframework-tutorial • 901\_static\_code\_analysis 3

- ✖ Multiple test cases with name 'Test Case 0201' (first occurrence in line 31) robocop(0801) [37, 1]
- ⚠ Found TODO in comment robocop(0701) [34, 7]
- ⚠ Too many blank lines at the end of file robocop(1010) [43, 1]

Further examples can be found in the RobotFramework AIO tutorial, chapter [901\\_static\\_code\\_analysis](#).

### How to configure?

Robocop contains a set of rules that are used to check the source files of the RobotFramework AIO. Not all of them are really useful and some of them are also against our company internal development rules. Therefore we have the need to exclude rules from Robocop execution.

Some rules can be configured (e.g. the rule checking the maximum number of characters within a line of code). Also here we have the need for careful adaptations.

When Robocop is triggered automatically within Visual Studio Code, then the configuration is done with the help of a `.robocop` file. This file has to be placed within the projects folder (see tutorial). To make Robocop results comparable this configuration file should not be modified - or at least should be kept aligned with the version all other project team members use.

## Command line

In addition to the automated triggering within Visual Studio Code Robocop can also be called in command line. This is useful

1. in case of a complete folder has to be checked in one step (to avoid the need to open every single source file inside separately),
2. in case of an alternative configuration is wanted (temporarily; to avoid to manipulate the standard configuration file),
3. in case of Robocop shall be triggered by automats like Jenkins,
4. in case of the Robocop results are needed within a log file (output to a log file needs to be configured separately).

To give it a try make a copy of the configuration file `.robocop` available within the tutorial, and give this copy any other name (e.g. `robocop.arg`).

Now Robocop can be called with command lines like this:

1.) *Simple check of single file with default configuration:*

```
"%RobotPythonPath%/python.exe" -m robocop "<path>/mytestfile.robot"
```

2.) *Check of single file with individual configuration taken from argument file:*

```
"%RobotPythonPath%/python.exe" -m robocop --argumentfile "<path>/robocop.arg" ↔  
↔ "<path>/mytestfile.robot"
```

3.) *Check of entire folder with individual configuration taken from argument file:*

```
"%RobotPythonPath%/python.exe" -m robocop --argumentfile "<path>/robocop.arg" "<folder>"
```

## How to activate?

In Visual Studio Code the automated triggering of Robocop is activated per default within

```
RobotFramework\robotvscode\data\user-data\User\settings.json
```

with the following switches set to `true` :

```
"robot.lint.enabled": true,  
"robot.lint.robocop.enabled": true,
```

## Chapter 3

# Library documentation

The following sections contain the documentation of additional libraries that are part of the RobotFramework AIO.

### RobotFramework AIO bundle

<b>RobotFramework AIO</b>
Version 0.5.1 (from 07/2022)

### Included libraries

<b>GenPackageDoc</b>
Version 0.26.0 (from 27.07.2022)
<a href="https://github.com/test-fullautomation/python-genpackagedoc">https://github.com/test-fullautomation/python-genpackagedoc</a>
<i>Documentation builder for Python packages</i>

<b>PythonExtensionsCollection</b>
Version 0.9.0 (from 27.07.2022)
<a href="https://github.com/test-fullautomation/python-extensions-collection">https://github.com/test-fullautomation/python-extensions-collection</a>
<i>Additional Python functions</i>

<b>RobotframeworkExtensions</b>
Version 0.8.0 (from 27.07.2022)
<a href="https://github.com/test-fullautomation/robotframework-extensions-collection">https://github.com/test-fullautomation/robotframework-extensions-collection</a>
<i>Additional Robot Framework keywords</i>

<b>JsonPreprocessor</b>
Version 0.1.3 (from 05.07.2022)
<a href="https://github.com/test-fullautomation/python-jsonpreprocessor">https://github.com/test-fullautomation/python-jsonpreprocessor</a>
<i>Preprocessor for json files</i>

<b>RobotFramework_Testsuites</b>
Version 0.2.2 (from 18.07.2022)
<a href="https://github.com/test-fullautomation/robotframework-testsuitesmanagement">https://github.com/test-fullautomation/robotframework-testsuitesmanagement</a>
<i>Functionality to manage RobotFramework testsuites</i>



**QConnectBase**

Version 1.1.0 (from 05.07.2022)

<https://github.com/test-fullautomation/robotframework-qconnect-base>*Robot Framework test library for TCP, SSH, serial connection***QConnectionDLTLibrary**

Version 1.1.0 (from 11.07.2022)

<https://sourcecode.socialcoding.bosch.com/projects/ROBFW/repos/robotframework-qconnect-dlt/browse>*Robot Framework test library for TCP, SSH, serial connection***RobotResults2RQM**

Version 1.1.1 (from 05.07.2022)

<https://github.com/test-fullautomation/robotframework-testresult2rqmtool>*Imports robot result(s) to IBM Rational Quality Manager (RQM)***RobotResults2DB**

Version 1.2.1 (from 05.07.2022)

<https://github.com/test-fullautomation/robotframework-testresultwebapptool>*Imports robot result(s) to TestResultWebApp database***TestResultWebApp**

Version 0.1.0 (from 04.07.2022)

<https://github.com/test-fullautomation/testresultwebapp>*Web based display of test results***TMLLog2RobotLog**

Version 1.1.0 (from 12.07.2022)

<https://sourcecode.socialcoding.bosch.com/projects/ROBFW/repos/robotframework-tmllog2robotlog/browse>*Convert TML-Framework results to Robot Framework results*

## 3.1 GenPackageDoc

**GenPackageDoc**

**v. 0.26.0**

Holger Queckenstedt

27.07.2022

# Contents

<b>1</b>	<b>Introduction</b>	<b>1</b>
<b>2</b>	<b>Description</b>	<b>2</b>
2.1	Repository content . . . . .	2
2.2	Documentation build process . . . . .	3
2.3	PDF document structure . . . . .	5
2.4	Examples . . . . .	6
2.4.1	Example 1: rst file . . . . .	6
2.4.2	Example 2: Python module . . . . .	6
2.5	Interface and module descriptions . . . . .	7
2.6	Runtime variables . . . . .	8
2.7	Syntax aspects . . . . .	9
2.7.1	Syntax extensions . . . . .	9
2.7.2	Examples . . . . .	9
<b>3</b>	<b>CDocBuilder.py</b>	<b>10</b>
3.1	Class: CDocBuilder . . . . .	10
3.1.1	Method: Build . . . . .	10
<b>4</b>	<b>CInterface.py</b>	<b>11</b>
4.1	Class: CInterface . . . . .	11
4.1.1	Method: GetLaTeXStyles . . . . .	11
<b>5</b>	<b>CPackageDocConfig.py</b>	<b>12</b>
5.1	Class: CPackageDocConfig . . . . .	12
5.1.1	Method: PrintConfig . . . . .	12
5.1.2	Method: PrintConfigKeys . . . . .	12
5.1.3	Method: Get . . . . .	12
5.1.4	Method: GetConfig . . . . .	12
<b>6</b>	<b>CPatterns.py</b>	<b>13</b>
6.1	Class: CPatterns . . . . .	13
6.1.1	Method: GetHeader . . . . .	13
6.1.2	Method: GetChapter . . . . .	14
6.1.3	Method: GetFooter . . . . .	14
<b>7</b>	<b>CSourceParser.py</b>	<b>15</b>
7.1	Class: CSourceParser . . . . .	15
7.1.1	Method: ParseSourceFile . . . . .	15

<i>CONTENTS</i>	<i>CONTENTS</i>
<b>8 Outlook</b>	<b>16</b>
<b>9 Appendix</b>	<b>18</b>
<b>10 History</b>	<b>19</b>
<hr/>	
B	

# Chapter 1

## Introduction

The Python package `GenPackageDoc` generates the documentation of Python modules. The content of this documentation is taken out of the docstrings of functions, classes and their methods.

It is possible to extend the documentation by the content of additional text files. The docstrings and also the additional text files have to be written in rst syntax (rst is the abbreviation for "re structured text", that is a certain markdown dialect).

The documentation is generated in two steps:

1. The rst sources are converted into LaTeX sources
2. The LaTeX sources are converted into a PDF document. This requires a separately installed LaTeX distribution (recommended: MiKTeX), that is **not** part of `GenPackageDoc`.

The sources of `GenPackageDoc` are available in the following GitHub repository:

[python-genpackagedoc](#)

The repository `python-genpackagedoc` uses it's own functionality to document itself and the contained Python package `GenPackageDoc`.

**Therefore the complete repository can be used as an example about writing a package documentation.**

It has to be considered, that the main goal of `GenPackageDoc` is to document Python sources that are stored within a repository, and therefore we have dependencies to the structure of the repository. For example: Configuration files with values that are specific for a repository, should not be installed. Such a specific configuration value is e.g. the name of the package or the name of the PDF document.

The impact is: There is a deep relationship between the repository containing the sources to be documented, and the sources and the configuration of `GenPackageDoc` itself. Therefore some manual preparations are necessary to use `GenPackageDoc` also in other repositories.

How to do this is explained in detail in the next chapters.

The outcome of all preparations of `GenPackageDoc` in your own repository is a PDF document like the one you are currently reading.

## Chapter 2

# Description

### 2.1 Repository content

*What is the content of the repository python-genpackagedoc?*

- Folder `GenPackageDoc`  
Contains the package code.  
*This folder is specific for the package.*
- Folder `config`  
Contains the repository configuration (e.g. the name of the package, the name of the repository, the author, and more ...).  
*This folder is specific for the repository.*
- Folder `additions`  
Contains additionally needed sources like setup related class definitions and sources, that are imported from other repositories - to make this repository stand alone
- Folder `packagedoc`  
Contains all package documentation related files, e.g. the `GenPackageDoc` configuration, additional input files and the generated documentation itself.  
*This folder is specific for the documentation.*
- Repository root folder
  - `genpackagedoc.py`  
Python script to start the documentation build
  - `setup.py`  
Python script to install the package sources. This includes the execution of `genpackagedoc.py`. Therefore building the documentation is part of the installation process.
  - `dump_repository_config.py`  
Little helper to dump the repository configuration to console

## 2.2 Documentation build process

*How do the files and folders listed above, belong together? What is the way, the information flows when the documentation is generated?*

- The process starts with the execution of `genpackagedoc.py` within the repository root folder.  
`genpackagedoc.py` can be used stand alone - but this script is also called by `setup.py`. The impact is that every installation includes an update of the documentation.

- `genpackagedoc.py` creates a repository configuration object

```
config/CRepositoryConfig.py
```

- The repository configuration object reads the static repository configuration values out of a separate json file

```
config/repository-config.json
```

- The repository configuration object adds dynamic values (like operating system specific settings and paths) to the repository configuration. Not all of them are required for the documentation build process, but the repository configuration also supports the setup process (`setup.py`).

There is one certain setting in the repository configuration file

```
config/repository-config.json,
```

that is essential for the documentation build process:

```
"PACKAGEDOC" : "../packagedoc"
```

This is the path to a folder, in which all further documentation related files are placed. In case of the path is relative, the reference is the position of `genpackagedoc.py`. It is required that within this folder the configuration file for the documentation build process

```
packagedoc-config.json
```

can be found. The name of this json file is fix!

- The configuration file `packagedoc-config.json` contains settings like
  - Paths to Python packages to be documented
  - Paths and names of additional rst files
  - Path and name of output folder (tex files and output PDF file)
  - User defined parameter (that can be defined here as global runtime variables and can be used in any rst code)
  - Basic settings related to the output PDF file (like document name, name of author, ...)
  - Path to LaTeX compiler  
(a *LaTeX distribution* is not part of `GenPackageDoc`)

Be aware of that the within `packagedoc-config.json` specified output folder

```
"OUTPUT" : "../build"
```

**will be deleted** at the beginning of the documentation build process! Make sure that you do not have any files inside this folder opened when you start the process. In case of the path is relative, the reference is the position of `genpackagedoc.py`. The complete path is created recursively.

**Further details are explained within the json file itself.**

- `genpackagedoc.py` also creates an own configuration object

```
GenPackageDoc/CPackageDocConfig.py
```

`CPackageDocConfig.py` takes over all repository configuration values, reads in the static `GenPackageDoc` configuration (`packagedoc-config.json`) and adds dynamically computed values like the full absolute paths belonging to the documentation build process. Also all command line parameters are resolved and checked.

The reference for all relative paths is the position of `genpackagedoc.py` (that is the repository root folder).

After the execution of `genpackagedoc.py` the resulting PDF document can be found under the specified name within the specified output folder ("OUTPUT"). This folder also contains all temporary files generated during the documentation build process.

Because the output folder is a temporary one, the PDF document is copied to the folder containing the package sources and therefore is included in the package installation. This is defined in the `GenPackageDoc` configuration, section "PDFDEST".

### Command line

Some configuration parameter predefined within `packagedoc.config.json`, can be overwritten in command line.

`--output`

Path and name of folder containing all output files.

`--pdfdest`

Path and name of folder in which the generated PDF file will be copied to (after this file has been created within the output folder).

*Caution:* The generated PDF file will per default be copied to the package folder within the repository. This is defined in `packagedoc.config.json`. The version of the PDF file within the package folder will be part of the installation (when using `setup.py`). When you change the PDF destination, then you get this file at another location - but this file will not be part of the installation any more. Installed will be the version, that is still present within the package folder of the repository. Please try to get the bottom of your motivation when you change this setting.

`--configdest`

Path and name of folder in which a dump of the current configuration will be copied to.

The configuration dump is part of the build output (section 'OUTPUT') and available in txt and in json format. It might be useful for further processes to have access to all details regarding the current documentation build.

`--strict`

If `True`, a missing LaTeX compiler aborts the process, otherwise the process continues.

### Example

```
genpackagedoc.py --output="../any/other/location" --pdfdest="../any/other/location"
↳ --configdest="../any/other/location" --strict=True
```

All listed parameters are optional. `GenPackageDoc` creates the complete output path (`--output`) recursively. Other destination folder (`--pdfdest` and `--configdest`) have to exist already.



## 2.3 PDF document structure

*How is the resulting PDF document structured? What causes an entry within the table of content of the PDF document?*

In the following we use terms taken over from the LaTeX world: *chapter*, *section* and *subsection*.

A *chapter* is the top level within the PDF document; a *section* is the level below *chapter*, a *subsection* is the level below *section*.

*The following assignments happen during the generation of a PDF document:*

- The content of every additionally included separate rst file is a *chapter*.
  - In case of you want to add another chapter to your documentation, you have to include another rst file.
  - The headline of the chapter is the name of the rst file (automatically).  
*Therefore the heading within an rst file has to start at section level!*
- The content of every included Python module is also a *chapter*.
  - The headline of the chapter is the name of the Python module (automatically).  
This means also that within the PDF document structure every Python module is at the same level as additionally included rst files.
- Within additionally included separate rst files sections and subsections can be defined by the following rst syntax elements for headings:
  - A line underlined with "=" characters is a section
  - A line underlined with "-" characters is a subsection
- Within the docstrings of Python modules the headings are added automatically (for functions, classes and methods)
  - Classes and functions are listed at section level (both classes and functions are assumed to be at the same level).
  - Class methods are listed at subsection level.

**Further nestings of headings are not supported** (because we do not want to overload the table of content).

## 2.4 Examples

### 2.4.1 Example 1: rst file

The text of this chapter is taken over from an rst file named `Description.rst`.

This rst file contains the following headlines:

```
Repository content
=====

Documentation build process
=====

PDF document structure
=====

Examples
=====

Example 1: rst file
-----

Example 2: Python module
-----
```

Because `Description.rst` is the second imported rst file, the chapter number is 2. The chapter headline is "Description" (the name of the rst file). The top level headlines *within* the rst file are at *section* level. The fourth section (Examples) contains two subsections.

The outcome is the following part of the table of content:

<b>2</b>	<b>Description</b>	<b>4</b>
2.1	Repository content . . . . .	4
2.2	Documentation build process . . . . .	5
2.3	PDF document structure . . . . .	6
2.4	Examples . . . . .	7
2.4.1	Example 1: rst file . . . . .	7
2.4.2	Example 2: Python module . . . . .	7

### 2.4.2 Example 2: Python module

Part of this documentation is a Python module with name `CDocBuilder.py` (listed in table of content at *chapter* level). This module contains a class with name `CDocBuilder` (listed in table of content at *section* level). The class `CDocBuilder` contains a method with name `Build` (listed in table of content at *subsection* level).

This causes the following entry within the table of contents:

<b>3</b>	<b>CDocBuilder.py</b>	<b>8</b>
3.1	Class: CDocBuilder . . . . .	8
3.1.1	Method: Build . . . . .	8

## 2.5 Interface and module descriptions

*How to describe an interface of a function or a method? How to describe a Python module?*

To have a unique look and feel of all interface descriptions, the following style is recommended:

### Example

```
"""
Description of function or method.

**Arguments:**

* ``input_param_1``

  / *Condition*: required / *Type*: str /

  Description of input_param_1.

* ``input_param_2``

  / *Condition*: optional / *Type*: bool / *Default*: False /

  Description of input_param_2.

**Returns:**

* ``return_param``

  / *Type*: str /

  Description of return_param.
"""
```

Some of the special characters used within the interface description, are part of the rst syntax. They will be explained in one of the next sections.

The docstrings containing the description, have to be placed directly in the next line after the `def` or `class` statement.

It is also possible to place a docstring at the top of a Python module. The exact position doesn't matter - but it has to be the first constant expression within the code. Within the documentation the content of this docstring is placed before the interface description and should contain general information belonging to the entire module.

The usage of such a docstring is an option.

## 2.6 Runtime variables

*What are "runtime variables" and how to use them in rst text?*

All configuration parameters of GenPackageDoc are taken out of four sources:

1. the static repository configuration  
config/repository.config.json
2. the dynamic repository configuration  
config/CRepositoryConfig.py
3. the static GenPackageDoc configuration  
packagedoc/packagedoc.config.json
4. the dynamic GenPackageDoc configuration  
GenPackageDoc/CPackageDocConfig.py

Some of them are runtime variables and can be accessed within rst text (within docstrings of Python modules and also within separate rst files).

This means it is possible to add configuration values automatically to the documentation.

This happens by encapsulating the runtime variable name in triple hashes. This "triple hash" syntax is introduced to make it easier to distinguish between the json syntax (mostly based on curly brackets) and additional syntax elements used within values of json keys.

The name of the repository e.g. can be added to the documentation with the following rst text:

```
The name of the repository is ###REPOSITORYNAME###.
```

This document contains a chapter "Appendix" at the end. This chapter is used to make the repository configuration a part of this documentation and can be used as example.

Additionally to the predefined runtime variables a user can add own ones.

See "PARAMS" within packagedoc.config.json.

All predefined runtime variables are written in capital letters. To make it easier for a developer to distinguish between predefined and user defined runtime variables, all user defined runtime variables have to be written in small letters completely.

Also the "DOCUMENT" keys within packagedoc.config.json are runtime variables.

Also within packagedoc.config.json the triple hash syntax can be used to access repository configuration values.

With this mechanism it is e.g. possible to give the output PDF document automatically the name of the package:

```
"DOCUMENT" : {
    "OUTPUTFILENAME" : "###PACKAGENAME###.tex",
```

## 2.7 Syntax aspects

Important to know about the syntax of Python and rst is:

- In both Python and rst the indentation of text is part of the syntax!
- The indentation of the triple quotes indicating the beginning and the end of a docstring has to follow the Python syntax rules.
- The indentation of the content of the docstring (= the interface description in rst format) has to follow the rst syntax rules. To avoid a needless indentation of the text within the resulting PDF document it is recommended to start the docstring text within the first column (or rather use the first column as reference for further indentations of rst text).
- In rst also blank lines are part of the syntax!

*Please be attentive while typing your documentation in rst format!*

### 2.7.1 Syntax extensions

GenPackageDoc extends the rst syntax by the following topics:

- *newline*  
A newline (line break) is realized by a slash (‘/’) at the end of a line containing any other rst text (this means: the slash must **not** be the only character in line). Internally this slash is mapped to the LaTeX command `\newline`.
- *vspace*  
An additional vertical space (size: the height of the ‘x’ character - depending on the current type and size of font) is realized by a single slash (‘/’). This slash must be the only character in line! Internally this slash is mapped to the LaTeX command `\vspace{1ex}`.
- *newpage*  
A newpage (page break) is realized by a double slash (‘//’). These two slashes must be the only characters in line! Internally this double slash is mapped to the LaTeX command `\newpage`.

These syntax extensions can currently be used in separate rst files only and are not available within docstrings of Python modules.

### 2.7.2 Examples

*(to be continued)*

## Chapter 3

# CDocBuilder.py

Python module containing all methods to generate tex sources.

### 3.1 Class: CDocBuilder

```
GenPackageDoc.CDocBuilder
```

Main class to build tex sources out of docstrings of Python modules and separate text files in rst format.

Depends on a json configuration file, provided by a `oPackageDocConfig` object (this includes the Repository configuration).

Method to execute: `Build()`

#### 3.1.1 Method: Build

**Arguments:**

(no arguments)

**Returns:**

- `bSuccess`  
/ Type: bool /  
Indicates if the computation of the method `sMethod` was successful or not.
- `sResult`  
/ Type: str /  
The result of the computation of the method `sMethod`.

## Chapter 4

# CInterface.py

Python module containing an interface for GenPackageDoc. This interface can be used to get access to the LaTeX stylesheets that are part of the GenPackageDoc installation.

### 4.1 Class: CInterface

```
GenPackageDoc.CInterface
```

#### 4.1.1 Method: GetLaTeXStyles

The LaTeX stylesheets are part of the installation of GenPackageDoc. In case of anyone else than GenPackageDoc needs these stylesheets, this method can be used to copy them to any other folder.

**Arguments:**

- `sDestination`  
/ *Condition*: required / *Type*: str /  
Path and name of a folder in which the styles folder from GenPackageDoc will be copied.

**Returns:**

- `bSuccess`  
/ *Type*: bool /  
Indicates if the computation of the method `sMethod` was successful or not.
- `sResult`  
/ *Type*: str /  
The result of the computation of the method `sMethod`.

## Chapter 5

# CPackageDocConfig.py

Python module containing the configuration for GenPackageDoc. This includes the repository configurantion and command line values.

### 5.1 Class: CPackageDocConfig

```
GenPackageDoc.CPackageDocConfig
```

#### 5.1.1 Method: PrintConfig

Prints all cofiguration values to console.

#### 5.1.2 Method: PrintConfigKeys

Prints all cofiguration key names to console.

#### 5.1.3 Method: Get

Returns the configuration value belonging to a key name.

#### 5.1.4 Method: GetConfig

Returns the complete configuration dictionary.



## Chapter 6

# CPatterns.py

Python module containing source patterns used to generate the tex file output.

### 6.1 Class: CPatterns

```
GenPackageDoc.CPatterns
```

The CPatterns class provides a set of LaTeX source patterns used to generate the tex file output.

All source patterns are accessible by corresponding Get methods. Some source patterns contain placeholder that will be replaced by input parameter of the Get method.

#### 6.1.1 Method: GetHeader

Defines the header of the main tex file.

**Arguments:**

- sTitle  
/ Condition: required / Type: str /  
The title of the output document (name of the described package)
- sVersion  
/ Condition: required / Type: str /  
The version of the output document (version of the described package)
- sAuthor  
/ Condition: required / Type: str /  
The author of the output document (author of the described package)
- sDate  
/ Condition: required / Type: str /  
The date of the output document (date of the described package)

**Returns:**

- sHeader  
/ Type: str /  
LaTeX code containing the header of main tex file.

### 6.1.2 Method: GetChapter

Defines single chapter of the main tex file.

A single chapter is equivalent to an additionally imported text file in rst format or equivalent to a single Python module within a Python package.

**Arguments:**

- `sHeadline`  
/ *Condition*: required / *Type*: str /  
The chapter headline (that is either the name of an additional rst file or the name of a Python module).
- `sDocumentName`  
/ *Condition*: required / *Type*: str /  
The name of a single tex file containing the chapter content. This file is imported in the main text file after the chapter headline that is set by `sHeadline`.

**Returns:**

- `sHeader`  
/ *Type*: str /  
LaTeX code containing the headline and the input of a single tex file.

### 6.1.3 Method: GetFooter

Defines the footer of the main tex file.

**Arguments:**

(no arguments)

**Returns:**

- `sFooter`  
/ *Type*: str /  
LaTeX code containing the footer of the main tex file.

## Chapter 7

# CSourceParser.py

Python module containing all methods to parse the documentation content of Python source files.

### 7.1 Class: CSourceParser

```
GenPackageDoc.CSourceParser
```

The `CSourceParser` class provides a method to parse the functions, classes and their methods together with the corresponding docstrings out of Python modules. The docstrings have to be written in rst syntax.

#### 7.1.1 Method: ParseSourceFile

The method `ParseSourceFile` parses the content of a Python module.

**Arguments:**

- `sFile`  
/ *Condition:* required / *Type:* str /  
Path and name of a single Python module.
- `bIncludePrivate`  
/ *Condition:* optional / *Type:* bool / *Default:* False /  
If False: private methods are skipped, otherwise they are included in documentation.
- `bIncludeUndocumented`  
/ *Condition:* optional / *Type:* bool / *Default:* True /  
If True: also classes and methods without docstring are listed in the documentation (together with a hint that information is not available), otherwise they are skipped.

**Returns:**

- `dictContent`  
/ *Type:* dict /  
A dictionary containing all the information parsed out of `sFile`.
- `bSuccess`  
/ *Type:* bool /  
Indicates if the computation of the method `sMethod` was successful or not.
- `sResult`  
/ *Type:* str /  
The result of the computation of the method `sMethod`.

## Chapter 8

# Outlook

### ToDo list:

- [01]  
Introduce `setup.py` including the execution of `genpackagedoc.py` and adding the generated PDF document to the installation.  
Introduce `README.rst` and `README.md`.  
10.05.2022: Setup process introduced and `README.rst` added
- [02]  
Currently it is hard coded, that private functions and methods are skipped. Therefore they are not part of the resulting PDF document.  
A configuration switch might be useful to give the user the ability to control this behavior.  
09.05.2022: Parameter 'INCLUDEPRIVATE' added
- [03]  
Currently it is implemented that also functions, classes and methods without docstrings are part of the resulting PDF document. They are listed together with the hint, that a docstring is not available.  
A configuration switch might be useful to give the user the ability to control this behavior.  
09.05.2022: Parameter 'INCLUDEUNDOCUMENTED' added
- [04]  
Currently it is implemented that for Python modules will be searched recursively within the given root folder. Maybe the algorithm also catches modules from which the user does not want `GenPackageDoc` to include them.  
A configuration exclude filter can be implemented to skip those files. Or maybe other way round: An include filter includes a subset of available files only.  
The same filter mechanism can be extended for the content of Python modules (= include/exclude functions, classes and methods).
- [05]  
Currently the configuration parameter for the documentation build process are taken from a json file `packagedoc.config.json`.  
It might be helpful to have the possibility to overwrite them in command line (e.g. for redirecting the path to the output folder without changing any code).  
31.05.2022: Implemented in v. 0.15.0
- [06]  
Introduce text boxes for warnings, errors and informations.  
19.05.2022: implemented in v. 0.12.0
- [07]  
The documentation build process allows relative paths only  
(in `packagedoc.config.json`).  
Maybe a mechanism is useful to allow absolute paths and paths based on environment variables also.  
01.06.2022: implemented in v. 0.16.0

CHAPTER 8. OUTLOOK

---

- [08]  
Explore further rst syntax elements like the code directive. Some of them produces LaTeX code that requires the include of additional LaTeX packages. Sometimes this causes errors that have to be fixed.  
05.05.2022: Python syntax highlighting realized
- [09]  
The documentation has to be extended by a set of rst examples (rst best practices).
- [10]  
A postprocessing for LaTeX code needs to be implemented:
  - Enable proper line breaks
  - Resolve the ambiguity of labels created automatically when the LaTeX code is generated (for every input file separately)
 10.05.2022: Experimental syntax extensions for `newline`, `newpage` and `vspace`  
 17.05.2022: Postprocessing for rst and tex sources added; "multiply-defined labels" fix.
- [11]  
Currently the docstrings of Python modules have to contain a heading for functions, classes and methods. The developer is responsible for that. Maybe it is not necessary to maintain these headings manually. It has to be investigated, if these headings can be added automatically by `GenPackageDoc`.  
06.05.2022: Headings are added automatically.
- [12]  
Currently the documentation of a single Python module starts at *function* or *class* level. This means it is not possible to provide common information about the Python module itself (placed **before** the content of the first function or class of the module). A way have to be found to add such content.  
06.05.2022: Implemented in version 0.4.0
- [13]  
The error handling needs to be extended!  
17.06.2022: Implemented in version 0.17.0
- [14]  
Take over the description of  

```
config/repository-config.json
```

 from inside this json file (comment blocks) to the main PDF document.
- [15]  
Reference section with useful links
- [16]  
History  
10.05.2022: History added
- [17]  
Debug switch to enable additional output
- [18]  
Parse decorators to identify Robot Framework keyword definitions
- [19]  
Selftest
- [20]  
Introduce a separate folder containing TeX styles - instead of having them hard coded within `CPatterns.py`.  
24.05.2022: implemented in v. 0.13.0

## Chapter 9

# Appendix

About this package:

Table 9.1: Package setup

Setup parameter	Value
Name	GenPackageDoc
Version	0.26.0
Date	27.07.2022
Description	Documentation builder for Python packages
Package URL	<a href="https://pypi.org/project/python-genpackagedoc/">python-genpackagedoc</a>
Author	Holger Queckenstedt
Email	<a href="mailto:Holger.Queckenstedt@de.bosch.com">Holger.Queckenstedt@de.bosch.com</a>
Language	Programming Language :: Python :: 3
License	License :: OSI Approved :: Apache Software License
OS	Operating System :: OS Independent
Python required	>=3.0
Development status	Development Status :: 3 - Alpha
Intended audience	Intended Audience :: Developers
Topic	Topic :: Software Development

## Chapter 10

# History

<b>0.1.0</b>	<a href="#">04/2022</a>
<i>Initial version</i>	
<b>0.2.0</b>	<a href="#">05.05.2022</a>
<i>Python syntax highlighting within code blocks added</i>	
<b>0.3.0</b>	<a href="#">06.05.2022</a>
<i>Automated headings for functions, classes and methods</i>	
<b>0.4.0</b>	<a href="#">06.05.2022</a>
<i>Possibility to describe complete Python modules added</i>	
<b>0.5.0</b>	<a href="#">09.05.2022</a>
<i>Parameter <code>INCLUDEPRIVATE</code> added</i>	
<b>0.6.0</b>	<a href="#">09.05.2022</a>
<i>Parameter <code>INCLUDEUNDOCUMENTED</code> added</i>	
<b>0.7.0</b>	<a href="#">10.05.2022</a>
<i>Setup process introduced and <code>README.rst</code> added; code maintenance</i>	
<b>0.8.0</b>	<a href="#">10.05.2022</a>
<i>Bugfixes and code maintenance; history added</i>	
<b>0.9.0</b>	<a href="#">10.05.2022</a>
<i>Layout maintenance and syntax extensions for <code>newline</code>, <code>newpage</code> and <code>vspace</code> reworked</i>	
<b>0.9.1</b>	<a href="#">11.05.2022</a>
<i>Documentation maintenance</i>	
<b>0.9.2</b>	<a href="#">16.05.2022</a>
<i>Fix: automated line breaks within code blocks</i>	
<b>0.10.0</b>	<a href="#">17.05.2022</a>
<i>Postprocessing for <code>rst</code> and <code>tex</code> sources added; 'multiply-defined labels' fix</i>	
<b>0.11.0</b>	<a href="#">18.05.2022</a>
<i>Import of <code>tex</code> files enabled</i>	
<b>0.12.0</b>	<a href="#">19.05.2022</a>
<ul style="list-style-type: none"> <li>- Admonitions added, based on <code>LaTeX</code> environment <code>tcolorbox</code></li> <li>- Layout adoptions in <code>titlepage</code></li> <li>- Page numbering fix in <code>TOC</code></li> </ul>	
<b>0.13.0</b>	<a href="#">24.05.2022</a>
<i><code>LaTeX</code> style definitions moved to separate folder</i>	
<b>0.14.0</b>	<a href="#">27.05.2022</a>

CHAPTER 10. HISTORY

---

- <i>LaTeX</i> compiler check added - Control parameter <i>STRICT</i> added to <i>packagedoc.config</i>	
<b>0.15.0</b>	31.05.2022
- Command line added - Separate <i>GenPackageDoc</i> configuration class added	
<b>0.16.0</b>	01.06.2022
Path computation reworked	
<b>0.17.0</b>	17.06.2022
- Configuration dump added - Code maintenance - Error handling extended	
<b>0.18.0</b>	20.06.2022
Added parameter to define an output folder for a dump of final configuration	
<b>0.19.0</b>	28.06.2022
- Method <i>GetLaTeXStyles</i> added - <i>PythonExtensionsCollection</i> updated to version 0.8.0	
<b>0.20.0</b>	29.06.2022
Document title bugfix: Added missing masking of underlines (required for <i>LaTeX</i> )	
<b>0.21.0</b>	12.07.2022
Separated file <i>preamble.tex</i>	
<b>0.22.0</b>	13.07.2022
- Maintenance of <i>preamble.tex</i> and <i>styles</i> folder - <i>setup.py</i> fix (install <i>tex</i> files also)	
<b>0.23.0</b>	13.07.2022
Maintenance of <i>preamble.tex</i>	
<b>0.24.0</b>	25.07.2022
Maintenance of <i>robotframeworkaio.sty</i> (line breaks in listings)	
<b>0.25.0</b>	27.07.2022
Layout maintenance of <i>RobotFramework AIO</i> syntax highlighting ( <i>.sty</i> files)	
<b>0.26.0</b>	27.07.2022
History reworked; <i>common.sty</i> introduced	

---

**GenPackageDoc.pdf***Created at 17.08.2022 - 14:09:30**by GenPackageDoc v. 0.26.0*

---



## 3.2 PythonExtensionsCollection

# PythonExtensionsCollection

**v. 0.9.0**

Holger Queckenstedt

27.07.2022

# Contents

<b>1</b>	<b>Introduction</b>	<b>1</b>
<b>2</b>	<b>Description</b>	<b>2</b>
2.1	Path normalization . . . . .	2
2.2	File access with CFile . . . . .	2
<b>3</b>	<b>CFile.py</b>	<b>7</b>
3.1	Class: enFileStatType . . . . .	7
3.2	Class: CFile . . . . .	7
3.2.1	Method: Close . . . . .	7
3.2.2	Method: Delete . . . . .	8
3.2.3	Method: Write . . . . .	8
3.2.4	Method: Append . . . . .	9
3.2.5	Method: ReadLines . . . . .	9
3.2.6	Method: GetFileInfo . . . . .	11
3.2.7	Method: CopyTo . . . . .	11
3.2.8	Method: MoveTo . . . . .	12
<b>4</b>	<b>CFolder.py</b>	<b>13</b>
4.1	Function: rm_dir_readonly . . . . .	13
4.2	Class: CFolder . . . . .	13
4.2.1	Method: Delete . . . . .	13
4.2.2	Method: Create . . . . .	14
4.2.3	Method: CopyTo . . . . .	14
<b>5</b>	<b>CString.py</b>	<b>16</b>
5.1	Class: CString . . . . .	16
5.1.1	Method: NormalizePath . . . . .	16
5.1.2	Method: DetectParentPath . . . . .	17
5.1.3	Method: StringFilter . . . . .	18
5.1.4	Method: FormatResult . . . . .	23
<b>6</b>	<b>CUtils.py</b>	<b>25</b>
6.1	Function: PrettyPrint . . . . .	25
6.2	Class: CTypePrint . . . . .	26
6.2.1	Method: TypePrint . . . . .	27
<b>7</b>	<b>Appendix</b>	<b>28</b>

<u>CONTENTS</u>	<u>CONTENTS</u>
<b>8 History</b>	<b>29</b>
<hr/>	
B	

# Chapter 1

## Introduction

The Python Extensions Collection package extends the functionality of Python by some useful functions that are not available in Python immediately.

This covers for example string operations like normalizing a path or searching for parent directories within a path.

The Python Extensions Collection contains several Python modules and every module has to be imported separately in case of the functions inside are needed.

### Module import

The modules of the Python Extension Collection and their methods can be accessed in the following ways:

#### *CFile*

```
from PythonExtensionsCollection.File.CFile import CFile
...
sFile = r"%TMP%\File.txt"
oFile = CFile(sFile)
```

Please consider that oFile is an instance of the class CFile - *and not a file handle*.

#### *CString*

```
from PythonExtensionsCollection.String.CString import CString
...
sPath = CString.NormalizePath(sPath)
...
bAck = CString.StringFilter(sString, ...)
...
sResult = CString.FormatResult(sMethod="", bSuccess=True, sResult="")
```

#### *CUtils*

```
from PythonExtensionsCollection.Utils.CUtils import *
...
PrettyPrint(oData)
```

## Chapter 2

# Description

### 2.1 Path normalization

It's not easy to handle paths - and especially the path separators - independent from the operating system.

Under Linux it is obvious that single slashes are used as separator within paths. Whereas the Windows explorer uses single backslashes. In both operating systems web addresses contains single slashes as separator when displayed in web browsers.

Using single backslashes within code - as content of string variables - is dangerous because the combination of a backslash and a letter can be interpreted as escape sequence - and this is maybe not the effect a user wants to have.

To avoid unwanted escape sequences backslashes have to be masked (by the usage of two of them: `\\`). But also this could not be the best solution because there are also applications (like the Windows explorer) that are not able to handle masked backslashes. They expect to get single backslashes within a path.

Preparing a path for best usage within code also includes collapsing redundant separators and up-level references. Python already provides functions to do this, but the outcome (path contains slashes or backslashes) depends on the operating system. And like already mentioned above also under Windows backslashes might not be the preferred choice.

It also has to be considered that redundant separators at the beginning of an address of a local network resource (like `\\server.com`) and or inside an internet address (like `https:\\server.com`) must **not** be collapsed! Unfortunately the Python function `normpath` does not consider this context.

To give the user full control about the format of a path, independent from the operating system and independent if it's a local path, a path to a local network resource or an internet address, the function `CString::NormalizePath()` provides lot's of parameters to influence the result.

### 2.2 File access with CFile

The motivation for the CFile module contains two main topics:

1. More user control by introducing further parameter for file access functions. With high priority CFile enables the user to take care about that nothing existing is overwritten accidentally.
2. Hide the file handles und use the mechanism of class variables to avoid access violations independent from the way different operation systems like Windows and Unix are handling this.

This shortens the code, eases the implementation and makes tests (in which this module is used) more stable.

*Define two variables with path and name of test files.*

Under Windows:

```
sFile_1 = r"%TMP%\CFile.TestFile.1.txt"
sFile_2 = r"%TMP%\CFile.TestFile.2.txt"
```

Or under Linux:

## CHAPTER 2. DESCRIPTION

## 2.2. FILE ACCESS WITH CFILE

```
sFile_1 = r"/tmp/CFile_TestFile_1.txt"
sFile_2 = r"/tmp/CFile_TestFile_2.txt"
```

The first class instance:

```
oFile_1 = CFile(sFile_1)
```

`oFile_1` is the instance of a class - *and not the file handle*. The file handle is hidden, the user has nothing to do with it.

Every class instance can work with one single file only (during the complete instance lifetime) and has exclusive access to this file.

No other class instance is allowed to use this file. Therefore the second line in the following code throws an exception:

```
oFile_1.A = CFile(sFile_1)
oFile_1.B = CFile(sFile_1)
```

It's more save to implement in this way:

```
try:
    oFile_1 = CFile(sFile_1)
except Exception as reason:
    print(str(reason))
```

For writing content to files two methods are available: `Write()` and `Append()`.

Using `Write()` causes the class to open the file for writing ('w') - in case of the file is not already opened for writing. Using `Append()` causes the class to open the file for appending ('a') - in case of the file is not already opened for appending.

Switching between `Write()` and `Append()` causes an intermediate file handle `close()` internally!

*Write some content to file:*

```
bSuccess, sResult = oFile_1.Write("A B C")
print(f"> sResult oFile_1.Write : '{sResult}' / bSuccess : {bSuccess}")
```

Most of the functions returns at least `bSuccess` and `sResult`.

- `bSuccess` is `True` in case of no error occurred.
- `bSuccess` is `False` in case of an error occurred.
- `bSuccess` is `None` in case of a very fatal error occurred (exceptions).
- `sResult` contains details about what happens during computation.

It is possible now to continue with using `oFile_1.Write("...")`; the content will be appended - as long as the file is still open for writing.

Some functions close the file handle (e.g. `ReadLines()`). Therefore sequences like

```
oFile_1.Write("...")
oFile_1.Readlines("...")
oFile_1.Write("...")
```

should be avoided - because the `Write()` after the `ReadLines()` starts the file from scratch and the file content written by the previous `Write()` calls is lost.

For appending content to a file use the function `Append()`.

*Append content to file:*

## CHAPTER 2. DESCRIPTION

## 2.2. FILE ACCESS WITH CFILE

```
bSuccess, sResult = oFile_1.Append("A B C")
```

For reading content from a file use the function `ReadLines()`.

*Read from file:*

```
listLines_1, bSuccess, sResult = oFile_1.ReadLines()
for sLine in listLines_1:
    print(f"{sLine}")
```

Additionally to `bSuccess` and `sResult` the function returns a list of lines.

Internally `ReadLines()` takes care about:

- Closing the file - in case the file is still opened
- Opening the file for reading
- Reading the content line by line until the end of file is reached
- Closing the file

To avoid code like this

```
for sLine in listLines_1:
    print(f"{sLine}")
```

it is also possible to let `ReadLines()` do this:

```
listLines_1, bSuccess, sResult = oFile_1.ReadLines(bToScreen=True)
```

A function to read a single line from file only is not available, but it is possible to use some filter parameter of `ReadLines()` to reduce the amount of content already during the file is read. This prevents the user from implementing further loops.

Let's assume the following:

- The file `sFile_1` contains empty lines
- The file `sFile_1` contains also lines, that are commented out (with a hash '#' at the beginning)
- We want `ReadLines()` to skip empty lines and lines that are commented out

This can be implemented in the following way.

*Read a subset of file content:*

```
listLines_1, bSuccess, sResult = oFile_1.ReadLines(bSkipBlankLines=True,
                                                    sComment='#')
```

It is a good practice to close file handles as soon as possible. Therefore `CFile` provides the possibility to do this explicitly.

*Close a file handle:*

```
bSuccess, sResult = oFile_1.Close()
```

This makes sense in case of later again access to this file is needed.

Additionally to that the file handle is closed implicitly:

- in case of it is required (e.g. when switching between read and write access),
- in case of the class instance is destroyed.

Therefore an alternative to the `Close()` function is the deletion of the class instance:

```
del oFile_1
```

This makes sense in case of access to this file is not needed any more.

It is recommended to prefer `del` (instead of `Close()`) to avoid to keep too much not used objects for a too long length of time in memory.

A file can be copied to another file.

*Copy a file:*

```
bSuccess, sResult = oFile_1.CopyTo(sFile_2)
```

The destination (`sFile_2` in the example above) can either be a full path and name of a file or the path only.

It makes a difference if the destination file exists or not. The optional parameter `bOverwrite` controls the behavior of `CopyTo()`.

The default is that it is not allowed to overwrite an existing destination file: `bOverwrite` is `False`. `CopyTo()` returns `bSuccess = False` in this case.

In case the user want to allow `CopyTo()` to overwrite existing destination files, it has to be coded explicitly:

```
bSuccess, sResult = oFile_1.CopyTo(sFile_2, bOverwrite=True)
```

A file can be moved to another file.

*Move a file:*

```
bSuccess, sResult = oFile_1.MoveTo(sFile_2)
```

Also `MoveTo()` supports `bOverwrite`. The behavior is the same as `CopyTo()`.

A file can be deleted.

*Delete a file:*

```
bSuccess, sResult = oFile_1.Delete()
```

It is possible to distinguish between two different motivations to delete a file:

1. *Explicitly do a deletion*

This requires that the file to be deleted, does exist.

2. *Making sure only that the files does not exist*

In this case it doesn't matter that maybe there is nothing to delete because the file already does not exist.

The optional parameter `bConfirmDelete` controls this behavior.

Default is that `Delete()` requires an existing file to delete:

```
bSuccess, sResult = oFile_1.Delete(bConfirmDelete=True)
```

In case of the file does not exist, `Delete()` returns `bSuccess = False`.

`Delete()` also returns `bSuccess = False|None` in case of an existing file cannot be deleted (e.g. because of an access violation).

If it doesn't matter if the file exists or not, it has to be coded explicitly:

```
bSuccess, sResult = oFile_1.Delete(bConfirmDelete=False)
```

In this case `Delete()` only returns `bSuccess = False|None` in case of an existing file cannot be deleted (e.g. because of an access violation).

**Avoid access violations**



Like already mentioned above every instance of `CFile` has an exclusive access to it's own file.

Only in case of `CopyTo()` and `MoveTo()` other files are involved: the destination files.

To avoid access violations it is not possible to copy or move a file to another file, that is under access of another instance of `CFile`.

In the following example `oFile_1.CopyTo(sFile_2)` returns `bSuccess = False` because `sFile_2` is already in access by `oFile_2`.

```
oFile_1 = CFile(sFile_1)
bSuccess, sResult = oFile_1.Write("A B C")

oFile_2 = CFile(sFile_2)
listLines_2, bSuccess, sResult = oFile_2.ReadLines()

bSuccess, sResult = oFile_1.CopyTo(sFile_2)

del oFile_1
del oFile_2
```

The solution is to delete the class instances as early as possible.

In the following example the copying is successful:

```
oFile_1 = CFile(sFile_1)
bSuccess, sResult = oFile_1.Write("A B C")

oFile_2 = CFile(sFile_2)
listLines_2, bSuccess, sResult = oFile_2.ReadLines()
del oFile_2

bSuccess, sResult = oFile_1.CopyTo(sFile_2)
del oFile_1
```

## Chapter 3

# CFile.py

### 3.1 Class: enFileStatType

```
PythonExtensionsCollection.File.CFile
```

The class `enFileStatType` defines the following file states:

- `closed`
- `openedforwriting`
- `openedforappending`
- `openedforreading`

### 3.2 Class: CFile

```
PythonExtensionsCollection.File.CFile
```

The class `CFile` provides a small set of file functions with extended parametrization (like switches defining if a file is allowed to be overwritten or not).

Most of the functions at least returns `bSuccess` and `sResult`.

- `bSuccess` is `True` in case of no error occurred.
- `bSuccess` is `False` in case of an error occurred.
- `bSuccess` is `None` in case of a very fatal error occurred (exceptions).
- `sResult` contains details about what happens during computation.

Every instance of `CFile` handles one single file only and forces exclusive access to this file.

It is not possible to create an instance of this class with a file that is already in use by another instance.

It is also not possible to use `CopyTo` or `MoveTo` to overwrite files that are already in use by another instance. This makes the file handling more save against access violations.

#### 3.2.1 Method: Close

Closes the opened file.

**Arguments:**

(no args)

**Returns:**

- `bSuccess`  
/ *Type*: bool /  
Indicates if the computation of the method was successful or not.
- `sResult`  
/ *Type*: str /  
The result of the computation of the method.

### 3.2.2 Method: Delete

Deletes the current file.

#### Arguments:

- `bConfirmDelete`  
/ *Condition*: optional / *Type*: bool / *Default*: True /  
Defines if it will be handled as error if the file does not exist.  
If True: If the file does not exist, the method indicates an error (`bSuccess = False`).  
If False: It doesn't matter if the file exists or not.

#### Returns:

- `bSuccess`  
/ *Type*: bool /  
Indicates if the computation of the method was successful or not.
- `sResult`  
/ *Type*: str /  
The result of the computation of the method.

### 3.2.3 Method: Write

Writes the content of a variable `Content` to file.

#### Arguments:

- `Content`  
/ *Condition*: required / *Type*: one of: str, list, tuple, set, dict, dotdict /  
If `Content` is not a string, the `Write` method resolves the data structure before writing the content to file.
- `nVSpaceAfter`  
/ *Condition*: optional / *Type*: int / *Default*: 0 /  
Adds vertical space `nVSpaceAfter` (= number of blank lines) after `Content`.
- `sPrefix`  
/ *Condition*: optional / *Type*: str / *Default*: None /  
`sPrefix` is added to every line of output (in case of `sPrefix` is not None').
- `bToScreen`  
/ *Condition*: optional / *Type*: bool / *Default*: False /  
Prints `Content` also to screen (in case of `bToScreen` is True).

#### Returns:

- `bSuccess`  
/ *Type*: bool /  
Indicates if the computation of the method was successful or not.
- `sResult`  
/ *Type*: str /  
The result of the computation of the method.

### 3.2.4 Method: Append

Appends the content of a variable `Content` to file.

#### Arguments:

- `Content`  
*/ Condition:* required */ Type:* one of: str, list, tuple, set, dict, dict /  
 If `Content` is not a string, the `Write` method resolves the data structure before writing the content to file.
- `nVSpaceAfter`  
*/ Condition:* optional */ Type:* int */ Default:* 0 /  
 Adds vertical space `nVSpaceAfter` (= number of blank lines) after `Content`.
- `sPrefix`  
*/ Condition:* optional */ Type:* str */ Default:* None /  
`sPrefix` is added to every line of output (in case of `sPrefix` is not None').
- `bToScreen`  
*/ Condition:* optional */ Type:* bool */ Default:* False /  
 Prints `Content` also to screen (in case of `bToScreen` is True).

#### Returns:

- `bSuccess`  
*/ Type:* bool /  
 Indicates if the computation of the method was successful or not.
- `sResult`  
*/ Type:* str /  
 The result of the computation of the method.

### 3.2.5 Method: ReadLines

Reads content from current file. Returns an array of lines together with `bSuccess` and `sResult` (feedback).

The method takes care of opening and closing the file. The complete file content is read by `ReadLines` in one step, but with the help of further parameters it is possible to reduce the content by including and excluding lines.

The logical join of all filter is: AND.

#### Arguments:

- `bCaseSensitive`  
*/ Condition:* optional */ Type:* bool */ Default:* True /  
 – If True, the standard filters work case sensitive, otherwise not.  
 – This has no effect to the regular expression based filters `sInclRegEx` and `sExclRegEx`.
- `bSkipBlankLines`  
*/ Condition:* optional */ Type:* bool */ Default:* False /  
 If True, blank lines will be skipped, otherwise not.
- `sComment`  
*/ Condition:* optional */ Type:* str */ Default:* None /  
 In case of a line starts with the string `sComment`, this line is skipped.
- `sStartsWith`  
*/ Condition:* optional */ Type:* str */ Default:* None /  
 – The criterion of this filter is fulfilled in case of the input string starts with the string `sStartsWith`

- More than one string can be provided (semicolon separated; logical join: OR)
- `sEndsWith`  
/ *Condition*: optional / *Type*: str / *Default*: None /
  - The criterion of this filter is fulfilled in case of the input string ends with the string `sEndsWith`
  - More than one string can be provided (semicolon separated; logical join: OR)
- `sStartsWith`  
/ *Condition*: optional / *Type*: str / *Default*: None /
  - The criterion of this filter is fulfilled in case of the input string starts with the string `sStartsWith`
  - More than one string can be provided (semicolon separated; logical join: AND)
- `sEndsWith`  
/ *Condition*: optional / *Type*: str / *Default*: None /
  - The criterion of this filter is fulfilled in case of the input string ends not with the string `sEndsWith`
  - More than one string can be provided (semicolon separated; logical join: AND)
- `sContains`  
/ *Condition*: optional / *Type*: str / *Default*: None /
  - The criterion of this filter is fulfilled in case of the input string contains the string `sContains` at any position
  - More than one string can be provided (semicolon separated; logical join: OR)
- `sContainsNot`  
/ *Condition*: optional / *Type*: str / *Default*: None /
  - The criterion of this filter is fulfilled in case of the input string does **not** contain the string `sContainsNot` at any position
  - More than one string can be provided (semicolon separated; logical join: AND)
- `sInclRegEx`  
/ *Condition*: optional / *Type*: str / *Default*: None /
  - *Include* filter based on regular expressions (consider the syntax of regular expressions!)
  - The criterion of this filter is fulfilled in case of the regular expression `sInclRegEx` matches the input string
  - Leading and trailing blanks within the input string are considered
  - `bCaseSensitive` has no effect
  - A semicolon separated list of several regular expressions is **not** supported
- `sExclRegEx`  
/ *Condition*: optional / *Type*: str / *Default*: None /
  - *Exclude* filter based on regular expressions (consider the syntax of regular expressions!)
  - The criterion of this filter is fulfilled in case of the regular expression `sExclRegEx` does **not** match the input string
  - Leading and trailing blanks within the input string are considered
  - `bCaseSensitive` has no effect
  - A semicolon separated list of several regular expressions is **not** supported
- `bLStrip`  
/ *Condition*: optional / *Type*: bool / *Default*: False /  
If True, leading spaces are removed from line before the filters are used, otherwise not.

- `bRStrip`  
/ *Condition*: optional / *Type*: bool / *Default*: True /  
If True, trailing spaces are removed from line before the filters are used, otherwise not.
- `bToScreen`  
/ *Condition*: optional / *Type*: bool / *Default*: False /  
If True, the content read from file is also printed to screen, otherwise not.

### 3.2.6 Method: GetFileInfo

Returns the following informations about the file (encapsulated within a dictionary `dFileInfo`):

**Returns:**

- Key `sFile`  
/ *Type*: str /  
Path and name of current file
- Key `bFileIsExisting`  
/ *Type*: bool /  
True if file is existing, otherwise False
- Key `sFileName`  
/ *Type*: str /  
The name of the current file (incl. extension)
- Key `sFileExtension`  
/ *Type*: str /  
The extension of the current file
- Key `sFileNameOnly`  
/ *Type*: str /  
The pure name of the current file (without extension)
- Key `sFilePath`  
/ *Type*: str /  
The the path to current file
- Key `bFilePathIsExisting`  
/ *Type*: bool /  
True if file path is existing, otherwise False

### 3.2.7 Method: CopyTo

Copies the current file to `sDestination`, that can either be a path without file name or a path together with a file name.

In case of the destination file already exists and `bOverwrite` is True, than the destination file will be overwritten.

In case of the destination file already exists and `bOverwrite` is False (default), than the destination file will not be overwritten and `CopyTo` returns `bSuccess = False`.

**Arguments:**

- `sDestination`  
/ *Condition*: required / *Type*: string /  
The path to destination file (either incl. file name or without file name)
- `bOverwrite`  
/ *Condition*: optional / *Type*: bool / *Default*: False /

- In case of the destination file already exists and `bOverwrite` is `True`, than the destination file will be overwritten.
- In case of the destination file already exists and `bOverwrite` is `False` (default), than the destination file will not be overwritten and `CopyTo` returns `bSuccess = False`.

**Returns:**

- `bSuccess`  
/ *Type*: `bool` /  
Indicates if the computation of the method was successful or not.
- `sResult`  
/ *Type*: `str` /  
The result of the computation of the method.

**3.2.8 Method: MoveTo**

Moves the current file to `sDestination`, that can either be a path without file name or a path together with a file name.

**Arguments:**

- `sDestination`  
/ *Condition*: required / *Type*: `string` /  
The path to destination file (either incl. file name or without file name)
- `bOverwrite`  
/ *Condition*: optional / *Type*: `bool` / *Default*: `False` /  
  - In case of the destination file already exists and `bOverwrite` is `True`, than the destination file will be overwritten.
  - In case of the destination file already exists and `bOverwrite` is `False` (default), than the destination file will not be overwritten and `MoveTo` returns `bSuccess = False`.

**Returns:**

- `bSuccess`  
/ *Type*: `bool` /  
Indicates if the computation was successful or not
- `sResult`  
/ *Type*: `str` /  
Contains details about what happens during computation

## Chapter 4

# CFolder.py

### 4.1 Function: `rm_dir_readonly`

Calls `os.chmod` in case of `shutil.rmtree` (within `Delete()`) throws an exception (making files writable).

### 4.2 Class: `CFolder`

```
PythonExtensionsCollection.Folder.CFolder
```

The class `CFolder` provides a small set of folder functions with extended parametrization (like switches defining if a folder is allowed to be overwritten or not).

Most of the functions at least returns `bSuccess` and `sResult`.

- `bSuccess` is `True` in case of no error occurred.
- `bSuccess` is `False` in case of an error occurred.
- `bSuccess` is `None` in case of a very fatal error occurred (exceptions).
- `sResult` contains details about what happens during computation.

Every instance of `CFolder` handles one single folder only and forces exclusive access to this folder.

It is not possible to create an instance of this class with a folder that is already in use by another instance.

The constructor of `CFolder` requires the input parameter `sFolder`, that is the path and the name of a folder that is handled by the current class instance.

#### 4.2.1 Method: `Delete`

Deletes the folder the current class instance contains.

**Arguments:**

- `bConfirmDelete`  
*/ Condition: optional / Type: bool / Default: True /*  
 Defines if it will be handled as error if the folder does not exist.  
 If `True`: If the folder does not exist, the method indicates an error (`bSuccess = False`).  
 If `False`: It doesn't matter if the folder exists or not.

**Returns:**

- `bSuccess`  
*/ Type: bool /*  
 Indicates if the computation of the method was successful or not.



- `sResult`  
/ *Type*: str /  
The result of the computation of the method.

#### 4.2.2 Method: Create

Creates the current folder `sFolder`.

##### Arguments:

- `bOverwrite`  
/ *Condition*: optional / *Type*: bool / *Default*: False /  
  - In case of the folder already exists and `bOverwrite` is `True`, than the folder will be deleted before creation.
  - In case of the folder already exists and `bOverwrite` is `False` (default), than the folder will not be touched.

In both cases the return value `bSuccess` is `True` - because the folder exists.

- `bRecursive`  
/ *Condition*: optional / *Type*: bool / *Default*: False /  
  - In case of `bRecursive` is `True`, than the complete destination path will be created (including all intermediate subfolders).
  - In case of `bRecursive` is `False`, than it is expected that the parent folder of the new folder already exists.

##### Returns:

- `bSuccess`  
/ *Type*: bool /  
Indicates if the computation of the method was successful or not.
- `sResult`  
/ *Type*: str /  
The result of the computation of the method.

#### 4.2.3 Method: CopyTo

Copies the current folder to `sDestination`, that has to be a path to a folder **within** the source folder will be copied to (with it's original name),

In case of the destination folder already exists and `bOverwrite` is `True`, than the destination folder will be overwritten.

In case of the destination folder already exists and `bOverwrite` is `False` (default), than the destination folder will not be overwritten and `CopyTo` returns `bSuccess = False`.

##### Arguments:

- `sDestination`  
/ *Condition*: required / *Type*: string /  
The path to destination folder
- `bOverwrite`  
/ *Condition*: optional / *Type*: bool / *Default*: False /  
  - In case of the destination folder already exists and `bOverwrite` is `True`, than the destination folder will be overwritten.
  - In case of the destination folder already exists and `bOverwrite` is `False` (default), than the destination folder will not be overwritten and `CopyTo` returns `bSuccess = False`.

**Returns:**

- `bSuccess`  
/ *Type*: bool /  
Indicates if the computation of the method was successful or not.
- `sResult`  
/ *Type*: str /  
The result of the computation of the method.

## Chapter 5

# CString.py

### 5.1 Class: CString

```
PythonExtensionsCollection.String.CString
```

The class `CString` contains some string computation methods like e.g. normalizing a path.

#### 5.1.1 Method: NormalizePath

Normalizes local paths, paths to local network resources and internet addresses

**Arguments:**

- `sPath`  
/ *Condition:* required / *Type:* str /  
The path to be normalized
- `bWin`  
/ *Condition:* optional / *Type:* bool / *Default:* False /  
If `True` then returned path contains masked backslashes as separator, otherwise slashes
- `sReferencePathAbs`  
/ *Condition:* optional / *Type:* str / *Default:* None /  
In case of `sPath` is relative and `sReferencePathAbs` (expected to be absolute) is given, then the returned absolute path is a join of both input paths
- `bConsiderBlanks`  
/ *Condition:* optional / *Type:* bool / *Default:* False /  
If `True` then the returned path is encapsulated in quotes - in case of the path contains blanks
- `bExpandEnvVars`  
/ *Condition:* optional / *Type:* bool / *Default:* True /  
If `True` then in the returned path environment variables are resolved, otherwise not.
- `bMask`  
/ *Condition:* optional / *Type:* bool / *Default:* True (requires `bWin=True`)/
  - If `bWin` is `True` and `bMask` is `True` then the returned path contains masked backslashes as separator.
  - If `bWin` is `True` and `bMask` is `False` then the returned path contains single backslashes only - this might be required for applications, that are not able to handle masked backslashes.
  - In case of `bWin` is `False` `bMask` has no effect.

**Returns:**

- `sPath`  
/ *Type*: str /  
The normalized path (is None in case of `sPath` is None)

### 5.1.2 Method: DetectParentPath

Computes the path to any parent folder inside a given path. Optionally `DetectParentPath` is able to search for files inside the parent folder.

#### Arguments:

- `sStartPath`  
/ *Condition*: required / *Type*: str /  
The path in which to search for a parent folder
- `sFolderName`  
/ *Condition*: required / *Type*: str /  
The name of the folder to search for within `sStartPath`. It is possible to provide more than one folder name separated by semicolon
- `sFileName`  
/ *Condition*: optional / *Type*: str / *Default*: None /  
The name of a file to search within the detected parent folder

#### Returns:

- `sDestPath`  
/ *Type*: str /  
Path and name of parent folder found inside `sStartPath`, None in case of `sFolderName` is not found inside `sStartPath`. In case of more than one parent folder is found `sDestPath` contains the first result and `listDestPaths` contains all results.
- `listDestPaths`  
/ *Type*: list /  
If `sFolderName` contains a single folder name this list contains only one element that is `sDestPath`. In case of `FolderName` contains a semicolon separated list of several folder names this list contains all found paths of the given folder names. `listDestPaths` is None (and not an empty list!) in case of `sFolderName` is not found inside `sStartPath`.
- `sDestFile`  
/ *Type*: str /  
Path and name of `sFileName`, in case of `sFileName` is given and found inside `listDestPaths`. In case of more than one file is found `sDestFile` contains the first result and `listDestFiles` contains all results. `sDestFile` is None in case of `sFileName` is None and also in case of `sFileName` is not found inside `listDestPaths` (and therefore also in case of `sFolderName` is not found inside `sStartPath`).
- `listDestFiles`  
/ *Type*: list /  
Contains all positions of `sFileName` found inside `listDestPaths`.  
`listDestFiles` is None (and not an empty list!) in case of `sFileName` is None and also in case of `sFileName` is not found inside `listDestPaths` (and therefore also in case of `sFolderName` is not found inside `sStartPath`).
- `sDestPathParent`  
/ *Type*: str /  
The parent folder of `sDestPath`, None in case of `sFolderName` is not found inside `sStartPath` (`sDestPath` is None).

### 5.1.3 Method: StringFilter

During the computation of strings there might occur the need to get to know if this string fulfils certain criteria or not. Such a criterion can e.g. be that the string contains a certain substring. Also an inverse logic might be required: In this case the criterion is that the string does **not** contain this substring.

It might also be required to combine several criteria to a final conclusion if in total the criterion for a string is fulfilled or not. For example: The string must start with the string *prefix* and must also contain either the string *substring1* or the string *substring2* but must also **not** end with the string *suffix*.

This method provides a bunch of predefined filters that can be used singly or combined to come to a final conclusion if the string fulfils all criteria or not.

The filters are divided into three different types:

1. Filters that are interpreted as raw strings (called 'standard filters'; no wild cards supported)
2. Filters that are interpreted as regular expressions (called 'regular expression based filters'; the syntax of regular expressions has to be considered)
3. Boolean switches (e.g. indicating if also an empty string is accepted or not)

The input string might contain leading and trailing blanks and tabs. This kind of horizontal space is removed from the input string before the standard filters start their work (except the regular expression based filters).

The regular expression based filters consider the original input string (including the leading and trailing space).

The outcome is that in case of the leading and trailing space shall be part of the criterion, the regular expression based filters can be used only.

It is possible to decide if the standard filters shall work case sensitive or not. This decision has no effect on the regular expression based filters.

The regular expression based filters always work with the original input string that is not modified in any way.

Except the regular expression based filters it is possible to provide more than one string for every standard filter (must be a semikolon separated list in this case). A semicolon that shall be part of the search string, has to be masked in this way: `\;`.

This method returns a boolean value that is `True` in case of all criteria are fulfilled, and `False` in case of some or all of them are not fulfilled.

The default value for all filters is `None` (except `bSkipBlankStrings`). In case of a filter value is `None` this filter has no influence on the result.

In case of all filters are `None` (default) the return value is `True` (except the string itself is `None` or the string is empty and `bSkipBlankStrings` is `True`).

In case of the string is `None`, the return value is `False`, because nothing concrete can be done with `None` strings.

Internally every filter has his own individual acknowledge that indicates if the criterion of this filter is fulfilled or not.

The meaning of *criterion fulfilled* of a filter is that the filter supports the final return value `bAck` of this method with `True`.

The final return value `bAck` of this method is a logical join (AND) of all individual acknowledges (except `bSkipBlankStrings` and `sComment`; in case of their criteria are **not** fulfilled, immediately `False` is returned).

Summarized:

- Filters are used to define *criteria*
- The return value of this method provides the *conclusion* - indicating if all criteria are fulfilled or not

**The following filters are available:**

#### `bSkipBlankStrings`

- Like already mentioned above leading and trailing spaces are removed from the input string at the beginning
- In case of the result is an empty string and `bSkipBlankStrings` is `True`, the method immediately returns `False` and all other filters are ignored

**sComment**

- In case of the input string starts with the string `sComment`, the method immediately returns `False` and all other filters are ignored
- Leading blanks within the input string have no effect
- The decision also depends on `bCaseSensitive`
- The idea behind this decision is: Ignore a string that is commented out

**sStartsWith**

- The criterion of this filter is fulfilled in case of the input string starts with the string `sStartsWith`
- Leading blanks within the input string have no effect
- The decision also depends on `bCaseSensitive`
- More than one string can be provided (semicolon separated; logical join: OR)

**sEndsWith**

- The criterion of this filter is fulfilled in case of the input string ends with the string `sEndsWith`
- Trailing blanks within the input string have no effect
- The decision also depends on `bCaseSensitive`
- More than one string can be provided (semicolon separated; logical join: OR)

**sStartsWithNot**

- The criterion of this filter is fulfilled in case of the input string does **not** start with the string `sStartsWithNot`
- Leading blanks within the input string have no effect
- The decision also depends on `bCaseSensitive`
- More than one string can be provided (semicolon separated; logical join: AND)

**sEndsWithNot**

- The criterion of this filter is fulfilled in case of the input string does **not** end with the string `sEndsWithNot`
- Trailing blanks within the input string have no effect
- The decision also depends on `bCaseSensitive`
- More than one string can be provided (semicolon separated; logical join: AND)

**sContains**

- The criterion of this filter is fulfilled in case of the input string contains the string `sContains` at any position
- Leading and trailing blanks within the input string have no effect
- The decision also depends on `bCaseSensitive`
- More than one string can be provided (semicolon separated; logical join: OR)

**sContainsNot**

- The criterion of this filter is fulfilled in case of the input string does **not** contain the string `sContainsNot` at any position
- Leading and trailing blanks within the input string have no effect
- The decision also depends on `bCaseSensitive`
- More than one string can be provided (semicolon separated; logical join: AND)

**sInclRegEx**

- *Include* filter based on regular expressions (consider the syntax of regular expressions!)
- The criterion of this filter is fulfilled in case of the regular expression `sInclRegEx` matches the input string
- Leading and trailing blanks within the input string are considered
- `bCaseSensitive` has no effect
- A semicolon separated list of several regular expressions is **not** supported

**sExclRegEx**

- *Exclude* filter based on regular expressions (consider the syntax of regular expressions!)
- The criterion of this filter is fulfilled in case of the regular expression `sExclRegEx` does **not** match the input string
- Leading and trailing blanks within the input string are considered
- `bCaseSensitive` has no effect
- A semicolon separated list of several regular expressions is **not** supported

**Further arguments:**

- `sString`  
/ *Condition*: required / *Type*: str /  
The input string that has to be investigated.
- `bCaseSensitive`  
/ *Condition*: optional / *Type*: bool / *Default*: True /  
If True, the standard filters work case sensitive, otherwise not.
- `bDebug`  
/ *Condition*: optional / *Type*: bool / *Default*: False /  
If True, additional output is printed to console (e.g. the decision of every single filter), otherwise not.

**Returns:**

- `bAck`  
/ *Type*: bool /  
Final statement about the input string `sString` after filter computation

**Examples:**

1. Returns True:

```
StringFilter(sString      = "Speed is 25 beats per minute",
             bCaseSensitive = True,
             bSkipBlankStrings = True,
             sComment      = None,
             sStartsWith    = "Sp",
             sEndsWith      = None,
             sStartsWithNot = None,
             sEndsWithNot   = None,
             sContains      = "beats",
             sContainsNot   = None,
             sInclRegEx     = None,
             sExclRegEx     = None)
```

2. Returns False:

```
StringFilter(sString      = "Speed is 25 beats per minute",
             bCaseSensitive = True,
             bSkipBlankStrings = True,
             sComment      = None,
             sStartsWith   = "Sp",
             sEndsWith     = None,
             sStartsWithNot = None,
             sEndsWithNot  = "minute",
             sContains     = "beats",
             sContainsNot  = None,
             sInclRegex    = None,
             sExclRegex    = None)
```

3. Returns True:

```
StringFilter(sString      = "Speed is 25 beats per minute",
             bCaseSensitive = True,
             bSkipBlankStrings = True,
             sComment      = None,
             sStartsWith   = None,
             sEndsWith     = None,
             sStartsWithNot = None,
             sEndsWithNot  = None,
             sContains     = None,
             sContainsNot  = "Beats",
             sInclRegex    = None,
             sExclRegex    = None)
```

4. Returns True:

```
StringFilter(sString      = "Speed is 25 beats per minute",
             bCaseSensitive = True,
             bSkipBlankStrings = True,
             sComment      = None,
             sStartsWith   = None,
             sEndsWith     = None,
             sStartsWithNot = None,
             sEndsWithNot  = None,
             sContains     = None,
             sContainsNot  = None,
             sInclRegex    = r"\d{2}",
             sExclRegex    = None)
```

5. Returns False:

```
StringFilter(sString      = "Speed is 25 beats per minute",
             bCaseSensitive = True,
             bSkipBlankStrings = True,
             sComment      = None,
             sStartsWith   = "Speed",
             sEndsWith     = None,
             sStartsWithNot = None,
             sEndsWithNot  = None,
             sContains     = None,
             sContainsNot  = None,
             sInclRegex    = r"\d{3}",
             sExclRegex    = None)
```

6. Returns False:



```
StringFilter(sString      = "Speed is 25 beats per minute",
             bCaseSensitive = True,
             bSkipBlankStrings = True,
             sComment      = None,
             sStartsWith   = "Speed",
             sEndsWith     = "minute",
             sStartsNotWith = "speed",
             sEndsNotWith  = None,
             sContains     = "beats",
             sContainsNot  = None,
             sInclRegex    = r"\d{2}",
             sExclRegex    = r"\d{2}")
```

7. Returns False:

```
StringFilter(sString      = " ",
             bCaseSensitive = True,
             bSkipBlankStrings = True,
             sComment      = None,
             sStartsWith   = None,
             sEndsWith     = None,
             sStartsNotWith = None,
             sEndsNotWith  = None,
             sContains     = None,
             sContainsNot  = None,
             sInclRegex    = None,
             sExclRegex    = None)
```

8. Returns False:

```
StringFilter(sString      = "# Speed is 25 beats per minute",
             bCaseSensitive = True,
             bSkipBlankStrings = True,
             sComment      = "#",
             sStartsWith   = None,
             sEndsWith     = None,
             sStartsNotWith = None,
             sEndsNotWith  = None,
             sContains     = "beats",
             sContainsNot  = None,
             sInclRegex    = None,
             sExclRegex    = None)
```

9. Returns False:

```
StringFilter(sString      = "   Alpha is not beta; and beta is not gamma   ",
             bCaseSensitive = True,
             bSkipBlankStrings = True,
             sComment      = None,
             sStartsWith   = None,
             sEndsWith     = None,
             sStartsNotWith = None,
             sEndsNotWith  = None,
             sContains     = "   Alpha   ",
             sContainsNot  = None,
             sInclRegex    = None,
             sExclRegex    = None)
```

Because blanks around search strings (here " Alpha ") are considered, whereas the blanks around the input string are removed before computation. Therefore " Alpha " cannot be found within the (shortened) input string.

10. This alternative solution returns True:

```
StringFilter(sString      = "  Alpha is not beta; and beta is not gamma  ",
             bCaseSensitive = True,
             bSkipBlankStrings = True,
             sComment      = None,
             sStartsWith   = None,
             sEndsWith     = None,
             sStartsWithNot = None,
             sEndsWithNot  = None,
             sContains     = None,
             sContainsNot  = None,
             sInclRegex    = r"\s{3}Alpha",
             sExclRegex    = None)
```

11. Returns True:

```
StringFilter(sString      = "Alpha is not beta; and beta is not gamma",
             bCaseSensitive = True,
             bSkipBlankStrings = True,
             sComment      = None,
             sStartsWith   = None,
             sEndsWith     = None,
             sStartsWithNot = None,
             sEndsWithNot  = None,
             sContains     = "beta; and",
             sContainsNot  = None,
             sInclRegex    = None,
             sExclRegex    = None)
```

The meaning of "beta; and" is: The criterion is fulfilled in case of either "beta" or " and" can be found. That's True in this example - but this has nothing to do with the fact, that also this string "beta; and" can be found. Here the semikolon is a separator character and therefore part of the syntax.

A semicolon that shall be part of the search string, has to be masked with '\;':

The meaning of "beta\; not" in the following example is: The criterion is fulfilled in case of "beta; not" can be found.

That's **not** True. Therefore the method returns False:

```
StringFilter(sString      = "Alpha is not beta; and beta is not gamma",
             bCaseSensitive = True,
             bSkipBlankStrings = True,
             sComment      = None,
             sStartsWith   = None,
             sEndsWith     = None,
             sStartsWithNot = None,
             sEndsWithNot  = None,
             sContains     = r"beta\; not",
             sContainsNot  = None,
             sInclRegex    = None,
             sExclRegex    = None)
```

#### 5.1.4 Method: FormatResult

Formats the result string sResult depending on bSuccess:

- bSuccess is True indicates *success*
- bSuccess is False indicates an *error*

- `bSuccess` is `None` indicates an *exception*

Additionally the name of the method that causes the result, can be provided (*optional*). This is useful for debugging.

**Arguments:**

- `sMethod`  
/ *Condition*: optional / *Type*: str / *Default*: (empty string) /  
Name of the method that causes the result.
- `bSuccess`  
/ *Condition*: optional / *Type*: bool / *Default*: True /  
Indicates if the computation of the method `sMethod` was successful or not.
- `sResult`  
/ *Condition*: optional / *Type*: str / *Default*: (empty string) /  
The result of the computation of the method `sMethod`.

**Returns:**

- `sResult`  
/ *Type*: str /  
The formatted result string.

## Chapter 6

# CUtils.py

### 6.1 Function: PrettyPrint

Wrapper function to create and use a `CTypePrint` object. This wrapper function is responsible for printing out the content to console and to a file (depending on input parameter).

The content itself is prepared by the method `TypePrint` of class `CTypePrint`. This happens `PrettyPrint` internally.

The idea behind the `PrettyPrint` function is to resolve also the content of composite data types and provide for every parameter inside:

- the type
- the total number of elements inside (e.g. the number of keys inside a dictionary)
- the counter number of the current element
- the value

Example call:

```
PrettyPrint(oData)
```

(with *oData* is a Python variable of any type)

The output can e.g. look like this:

```
[DICT] (3/1) > {K1} [STR] : 'Val1'
[DICT] (3/2) > {K2} [LIST] (4/1) > [INT] : 1
[DICT] (3/2) > {K2} [LIST] (4/2) > [STR] : 'A'
[DICT] (3/2) > {K2} [LIST] (4/3) > [INT] : 2
[DICT] (3/2) > {K2} [LIST] (4/4) > [TUPLE] (2/1) > [INT] : 9
[DICT] (3/2) > {K2} [LIST] (4/4) > [TUPLE] (2/2) > [STR] : 'Z'
[DICT] (3/3) > {K3} [INT] : 5
```

Every line of output has to be interpreted strictly from left to right.

For example the meaning of the fifth line of output

```
[DICT] (3/2) > {K2} [LIST] (4/4) > [TUPLE] (2/1) > [INT] : 9
```

is:

- The type of input parameter (*oData*) is dict
- The dictionary contains 3 keys
- The current line gives information about the second key of the dictionary

- The name of the second key is 'K2'
- The value of the second key is of type `list`
- The list contains 4 elements
- The current line gives information about the fourth element of the list
- The fourth element of the list is of type `tuple`
- The tuple contains 2 elements
- The current line gives information about the first element of the tuple
- The first element of the tuple is of type `int` and has the value 9

Types are encapsulated in square brackets, counter in round brackets and key names are encapsulated in curly brackets.

#### Arguments:

- `oData`  
/ *Condition*: required / *Type*: (any Python data type) /  
A variable of any Python data type.
- `hOutputFile`  
/ *Condition*: optional / *Type*: file handle / *Default*: None /  
If handle is not None the content is written to this file, otherwise not.
- `bToConsole`  
/ *Condition*: optional / *Type*: bool / *Default*: True /  
If True the content is written to console, otherwise not.
- `nIndent`  
/ *Condition*: optional / *Type*: int / *Default*: 0 /  
Sets the number of additional blanks at the beginning of every line of output (indentation).
- `sPrefix`  
/ *Condition*: optional / *Type*: str / *Default*: None /  
Sets a prefix string that is added at the beginning of every line of output.
- `bHexFormat`  
/ *Condition*: optional / *Type*: bool / *Default*: False /  
If True the output is printed in hexadecimal format (but valid for strings only).

#### Returns:

- `listOutLines` (*list*)  
/ *Type*: list /  
List of lines containing the prepared output

## 6.2 Class: CTypePrint

```
PythonExtensionsCollection.Uutils.CUtils
```

The class `CTypePrint` provides a method (`TypePrint`) to compute the following data:

- the type
- the total number of elements inside (e.g. the number of keys inside a dictionary)
- the counter number of the current element
- the value

of simple and composite data types.

The call of this method is encapsulated within the function `PrettyPrint` inside this module.

### 6.2.1 Method: TypePrint

The method `TypePrint` computes details about the input variable `oData`.

**Arguments:**

- `oData`  
/ *Condition*: required / *Type*: any Python data type /  
Python variable of any data type.
- `bHexFormat`  
/ *Condition*: optional / *Type*: bool / *Default*: False /  
If `True` the output is provide in hexadecimal format.

**Returns:**

- `listOutLines`  
/ *Type*: list /  
List of lines containing the resolved content of `oData`.

## Chapter 7

# Appendix

About this package:

Table 7.1: Package setup

Setup parameter	Value
Name	PythonExtensionsCollection
Version	0.9.0
Date	27.07.2022
Description	Additional Python functions
Package URL	<a href="#">python-extensions-collection</a>
Author	Holger Queckenstedt
Email	<a href="mailto:Holger.Queckenstedt@de.bosch.com">Holger.Queckenstedt@de.bosch.com</a>
Language	Programming Language :: Python :: 3
License	License :: OSI Approved :: Apache Software License
OS	Operating System :: OS Independent
Python required	>=3.0
Development status	Development Status :: 4 - Beta
Intended audience	Intended Audience :: Developers
Topic	Topic :: Software Development

## Chapter 8

# History

<b>0.1.0</b>	08/2021
<i>Initial version</i>	
<b>0.2.0</b>	02/2022
<i>Code maintenance</i>	
<b>0.3.0</b>	20.05.2022
<i>Documentation tool chain switched to GenPackageDoc</i>	
<b>0.4.0</b>	24.05.2022
- Documentation rebuild with GenPackageDoc v. 0.13.0 - Code maintenance	
<b>0.5.0</b>	31.05.2022
<i>Adapted to GenPackageDoc v. 0.15.0</i>	
<b>0.6.0</b>	02.06.2022
- Documentation rebuild with GenPackageDoc v. 0.16.0 - Code maintenance	
<b>0.7.0</b>	10.06.2022
<i>Module CFolder added (with methods: Create and Delete</i>	
<b>0.8.0</b>	28.06.2022
<i>Module CFolder: Method: CopyTo added</i>	
<b>0.9.0</b>	27.07.2022
<i>History reworked (requires GenPackageDoc v. 0.26.0 at least)</i>	

---

**PythonExtensionsCollection.pdf***Created at 17.08.2022 - 14:09:42**by GenPackageDoc v. 0.26.0*

---



### 3.3 RobotframeworkExtensions

## RobotframeworkExtensions

**v. 0.8.0**

Holger Queckenstedt

27.07.2022

# Contents

<b>1</b>	<b>Introduction</b>	<b>1</b>
<b>2</b>	<b>Collection.py</b>	<b>2</b>
2.1	Class: Collection . . . . .	2
2.1.1	Method: pretty_print . . . . .	2
2.1.2	Method: normalize_path . . . . .	3
<b>3</b>	<b>Appendix</b>	<b>5</b>
<b>4</b>	<b>History</b>	<b>6</b>

# Chapter 1

## Introduction

The *Robotframework Extensions Collection* extends the functionality of the Robotframework by some keywords providing features, that are implemented in the *Python Extensions Collection*.

The goal behind these extensions is to have certain functionality available in both: pure Python applications and Robotframework.

The *Robotframework Extensions Collection* requires an installed *Python Extensions Collection*, that can be found in this repository:

[python-extensions-collection](#)

## Chapter 2

# Collection.py

The Collection module is the interface between the Python Extensions Collection and the Robotframework. This library containing the keyword definitions, can be imported in the following way:

```
Library      RobotframeworkExtensions.Collection      WITH NAME      rf.extensions
```

### 2.1 Class: Collection

```
RobotframeworkExtensions.Collection
```

Module main class

#### 2.1.1 Method: pretty\_print

The `pretty_print` keyword logs the content of parameters of any Python data type (input: `oData`). Simple data types are logged directly. Composite data types are resolved before logging. The output contains for every parameter: the value, the type and counter values (in case of composite data types). The trace level for output is INFO. The output is also returned as list of strings.

**Arguments:**

- `oData`  
/ *Condition:* required / *Type:* any Python type /  
Data to be pretty printed

**Returns:**

- `listOutLines` (*list*)  
/ *Type:* list /  
List of strings containing the resolved data structure of `oData` (same content as printed to console).

**Example:**

Variable of Python type list:

```
set_test_variable    @{aItems}    String
...                  ${{25}}
...                  ${{True}}
...                  ${{None}}
```

Call of `pretty_print` keyword:

```
rf.extensions.pretty_print    ${aItems}
```

Output:

```
INFO - [LIST] (4/1) > [STR]   : 'String'
INFO - [LIST] (4/2) > [INT]   : 25
INFO - [LIST] (4/3) > [BOOL]  : True
INFO - [LIST] (4/4) > [NONE]  : None
```

### 2.1.2 Method: `normalize_path`

The `normalize_path` keyword normalizes local paths, paths to local network resources and internet addresses

#### Arguments:

- `sPath`  
/ Condition: required / Type: str /  
The path to be normalized
- `bWin`  
/ Condition: optional / Type: bool / Default: False /  
If True then the returned path contains masked backslashes as separator, otherwise slashes
- `sReferencePathAbs`  
/ Condition: optional / Type: str / Default: None /  
In case of `sPath` is relative and `sReferencePathAbs` (expected to be absolute) is given, then the returned absolute path is a join of both input paths
- `bConsiderBlanks`  
/ Condition: optional / Type: bool / Default: False /  
If True then the returned path is encapsulated in quotes - in case of the path contains blanks
- `bExpandEnvVars`  
/ Condition: optional / Type: bool / Default: True /  
If True then in the returned path environment variables are resolved, otherwise not.
- `bMask`  
/ Condition: optional / Type: bool / Default: True (requires `bWin=True`) /  
If `bWin` is True and `bMask` is True then the returned path contains masked backslashes as separator.  
If `bWin` is True and `bMask` is False then the returned path contains single backslashes only - this might be required for applications, that are not able to handle masked backslashes.  
In case of `bWin` is False `bMask` has no effect.

#### Returns:

- `sPath`  
/ Type: str /  
The normalized path (is None in case of `sPath` is None)

#### Example 1:

Variable containing a path with:

- different types of path separators
- redundant path separators (but backslashes have to be masked in the definition of the variable, this is *not* an unwanted redundancy)

- up-level references

```
set_test_variable    ${sPath}    C:\\subfolder1\\../subfolder2\\\\../subfolder3\\
```

Printing the content of `sPath` shows how the path looks like when the masking of the backslashes is resolved:

```
C:\subfolder1\\../subfolder2\../subfolder3\
```

Usage of the `normalize_path` keyword:

```
${sPath}    rf.extensions.normalize_path    ${sPath}
```

Result (content of `sPath`):

```
C:/subfolder3
```

In case we need the Windows version (with masked backslashes instead of slashes):

```
${sPath}    rf.extensions.normalize_path    ${sPath}    bWin=${True}
```

Result (content of `sPath`):

```
C:\\subfolder3
```

The masking of backslashes can be deactivated:

```
${sPath}    rf.extensions.normalize_path    ${sPath}    bWin=${True}    bMask=${False}
```

Result (content of `sPath`):

```
C:\subfolder3
```

### Example 2:

Variable containing a path of a local network resource:

```
set_test_variable    ${sPath}    \\\anyserver.com\part1//part2\\\part3/part4
```

Result of normalization:

```
//anyserver.com/part1/part2/part3/part4
```

### Example 3:

Variable containing an internet address:

```
set_test_variable    ${sPath}    http:\\\\anyserver.com\part1//part2\\\part3/part4
```

Result of normalization:

```
http://anyserver.com/part1/part2/part3/part4
```

## Chapter 3

# Appendix

About this package:

Table 3.1: Package setup

Setup parameter	Value
Name	RobotframeworkExtensions
Version	0.8.0
Date	27.07.2022
Description	Additional Robot Framework keywords
Package URL	<a href="#">robotframework-extensions-collection</a>
Author	Holger Queckenstedt
Email	<a href="mailto:Holger.Queckenstedt@de.bosch.com">Holger.Queckenstedt@de.bosch.com</a>
Language	Programming Language :: Python :: 3
License	License :: OSI Approved :: Apache Software License
OS	Operating System :: OS Independent
Python required	>=3.0
Development status	Development Status :: 4 - Beta
Intended audience	Intended Audience :: Developers
Topic	Topic :: Software Development

## Chapter 4

# History

<b>0.1.0</b>	01/2022
<i>Initial version</i>	
<b>0.2.0</b>	03/2022
<i>Setup maintenance</i>	
<b>0.3.0</b>	05/2022
<i>Documentation tool chain switched to GenPackageDoc</i>	
<b>0.4.0</b>	24.05.2022
<ul style="list-style-type: none"> <li>- Documentation rebuild with GenPackageDoc v. 0.13.0</li> <li>- Code maintenance</li> </ul>	
<b>0.5.0</b>	31.05.2022
<i>Adapted to GenPackageDoc v. 0.15.0</i>	
<b>0.6.0</b>	02.06.2022
<ul style="list-style-type: none"> <li>- Documentation rebuild with GenPackageDoc v. 0.16.0</li> <li>- Code maintenance</li> </ul>	
<b>0.7.0</b>	28.06.2022
<i>PythonExtensionsCollection updated to version 0.8.0</i>	
<b>0.8.0</b>	27.07.2022
<i>History reworked (requires GenPackageDoc v. 0.26.0 at least)</i>	

---

**RobotframeworkExtensions.pdf***Created at 17.08.2022 - 14:09:53**by GenPackageDoc v. 0.26.0*

---



## 3.4 JsonPreprocessor

# JsonPreprocessor

**v. 0.1.3**

Mai Dinh Nam Son

05.07.2022

# Contents

<b>1</b>	<b>Introduction</b>	<b>1</b>
<b>2</b>	<b>Description</b>	<b>2</b>
<b>3</b>	<b>CJsonPreprocessor.py</b>	<b>3</b>
3.1	Class: CSyntaxType . . . . .	3
3.2	Class: CPythonJSONDecoder . . . . .	3
3.2.1	Method: custom_scan_once . . . . .	3
3.3	Class: CJsonPreprocessor . . . . .	3
3.3.1	Method: jsonLoad . . . . .	4
<b>4</b>	<b>Appendix</b>	<b>5</b>
<b>5</b>	<b>History</b>	<b>6</b>

# Chapter 1

## Introduction

*Json Preprocessor*

!!! add introduction - if wanted !!

## Chapter 2

# Description

The json preprocessor:



TO BE CONTINUED

## Chapter 3

# CJsonPreprocessor.py

### 3.1 Class: CSyntaxType

```
JsonPreprocessor.CJsonPreprocessor
```

### 3.2 Class: CPythonJSONDecoder

```
JsonPreprocessor.CJsonPreprocessor
```

**Method: PythonJSONDecoder** Add python data types and syntax to json. True, False and None will be accepted as json syntax elements.

**Args: json.JSONDecoder (*object*)** Decoder object provided by `json.loads`

#### 3.2.1 Method: custom\_scan\_once

### 3.3 Class: CJsonPreprocessor

```
JsonPreprocessor.CJsonPreprocessor
```

CJsonPreprocessor extends the syntax of json.

Features are

- Allow c/c++-style comments within json files.  
// single line or part of single line and /\* \*/ multiline comments are possible
- Allow to import json files into json files  
"[import]" : "relative/absolute path", imports another json file to exactly this location.  
%envariable% and \${envariable} can be used, too.
- Allow use of variables within json files  
In any place the syntax \${basenode.subnode. ... nodename} allows to reference an already existing variable.  
Example:

```
{
  "basenode" : {
    subnode : {
      "myparam" : 5
    },
  },
  "myVar" : "${basenode.subnode.myparam}"
}
```

- Allow python data types True, False and None

### 3.3.1 Method: jsonLoad

**Method:** `jsonLoad` This function is the entry point of JsonPreprocessor.

It loads the json file, preprocesses it and returns the preprocessed result as data structure.

**Args:** `jFile` (*string*) relative/absolute path to main json file.

`%envvariable%` and `${envvariable}` can be used, too in order to access environment variables.

**Returns:** `oJson` (*dict*) preprocessed json file(s) as data structure

## Chapter 4

# Appendix

About this package:

Table 4.1: Package setup

Setup parameter	Value
Name	JsonPreprocessor
Version	0.1.3
Date	05.07.2022
Description	Preprocessor for json files
Package URL	<a href="#">python-jsonpreprocessor</a>
Author	Mai Dinh Nam Son
Email	<a href="mailto:son.maidinhnam@vn.bosch.com">son.maidinhnam@vn.bosch.com</a>
Language	Programming Language :: Python :: 3
License	License :: OSI Approved :: Apache Software License
OS	Operating System :: OS Independent
Python required	>=3.0
Development status	Development Status :: 4 - Beta
Intended audience	Intended Audience :: Developers
Topic	Topic :: Software Development

## Chapter 5

# History

<b>0.1.0</b>	01/2022
<i>Initial version</i>	

---

**JsonPreprocessor.pdf***Created at 17.08.2022 - 14:10:03**by GenPackageDoc v. 0.26.0*

---



## 3.5 RobotFramework\_Testsuites

# RobotFramework\_Testsuites

**v. 0.2.2**

Mai Dinh Nam Son

18.07.2022

# Contents

<b>1</b>	<b>Introduction</b>	<b>1</b>
<b>2</b>	<b>Description</b>	<b>2</b>
<b>3</b>	<b>CConfig.py</b>	<b>3</b>
3.1	Class: dotdict . . . . .	3
3.2	Class: CConfig . . . . .	3
3.2.1	Method: loadCfg . . . . .	3
3.2.2	Method: updateCfg . . . . .	3
3.2.3	Method: verifyRbfwVersion . . . . .	3
3.2.4	Method: versioncontrol_error . . . . .	3
<b>4</b>	<b>COnFailureHandle.py</b>	<b>4</b>
4.1	Class: COnFailureHandle . . . . .	4
4.1.1	Method: is_noney . . . . .	4
4.1.2	Method: register_keyword_run_on_failure . . . . .	4
<b>5</b>	<b>CSetup.py</b>	<b>5</b>
5.1	Class: CSetupKeywords . . . . .	5
5.1.1	Method: testsuite.teardown . . . . .	5
5.1.2	Method: testcase_setup . . . . .	5
5.1.3	Method: testcase_teardown . . . . .	5
5.1.4	Method: update_config . . . . .	5
5.2	Class: CGeneralKeywords . . . . .	5
<b>6</b>	<b>CStruct.py</b>	<b>6</b>
6.1	Class: CStruct . . . . .	6
<b>7</b>	<b>Event.py</b>	<b>7</b>
7.1	Class: Event . . . . .	7
7.1.1	Method: trigger . . . . .	7
<b>8</b>	<b>ScopeEvent.py</b>	<b>8</b>
8.1	Class: ScopeEvent . . . . .	8
8.1.1	Method: trigger . . . . .	8
8.2	Class: ScopeStart . . . . .	8
8.3	Class: ScopeEnd . . . . .	8
<b>9</b>	<b>__init__.py</b>	<b>9</b>
9.1	Function: on . . . . .	9

CONTENTS	CONTENTS
9.2 Function: <code>dispatch</code> . . . . .	9
9.3 Function: <code>register_event</code> . . . . .	9
<b>10 LibListener.py</b>	<b>10</b>
10.1 Class: <code>LibListener</code> . . . . .	10
<b>11 __init__.py</b>	<b>11</b>
11.1 Class: <code>RobotFramework_Testsuites</code> . . . . .	11
11.1.1 Method: <code>get_keyword_tags</code> . . . . .	11
11.1.2 Method: <code>get_keyword_documentation</code> . . . . .	11
11.1.3 Method: <code>failure_occurred</code> . . . . .	11
11.2 Class: <code>CTestsuitesCfg</code> . . . . .	11
<b>12 version.py</b>	<b>12</b>
12.1 Function: <code>robFWaio_version</code> . . . . .	12
<b>13 Appendix</b>	<b>13</b>
<b>14 History</b>	<b>14</b>
<hr/>	
B	

# Chapter 1

## Introduction

*RobotFramework.Testsuites*

!!! add introduction - if wanted !!

# Chapter 2

## Description

The RobotFramework AIO testsuites management:  
TO BE CONTINUED

## Chapter 3

# CConfig.py

### 3.1 Class: dotdict

```
RobotFramework.Testsuites.Config.CConfig
```

### 3.2 Class: CConfig

```
RobotFramework.Testsuites.Config.CConfig
```

Defines the properties of configuration Holds the identified config files. Level1 is highest priority, Level4 is lowest priority.

(remaining content needs to be fixed and restored)

#### 3.2.1 Method: loadCfg

#### 3.2.2 Method: updateCfg

staticmethod updateParams: This method updates preprocessor, global or local params base on ROBFW local config or any json config file according to purpose of specific testsuite.

**Args:** sUpdateCfgFile: str

**Returns:** None

#### 3.2.3 Method: verifyRbfwVersion

Validate the current robotframework version with maximum and minimum version (if provided in the configuration file). In case the current version is not between min and max version, then the execution of testsuite is terminated with "unknown" state Method: bValidateMinVersion -----

Validate current version with required minimum version. Method: bValidateMaxVersion -----

Validate current version with required maximum version. Method: bValidateSubVersion -----

Validate the format of provided sub version and parse it into sub tuple for version comparison. Method: tupleVersion -----

Return a tuple which contains the (major, minor, patch) version.

(remaining content needs to be fixed and restored)

#### 3.2.4 Method: versioncontrol\_error

Wrapper version control error log: Log error message of version control due to reason and set to unknown state. reason can only be "conflict\_min", "conflict\_max" and "wrong\_minmax".

## Chapter 4

# COnFailureHandle.py

### 4.1 Class: COnFailureHandle

```
RobotFramework.Testsuites.Keywords.COnFailureHandle
```

4.1.1 Method: `is_noney`

4.1.2 Method: `register_keyword_run_on_failure`

TBD

## Chapter 5

# CSetup.py

### 5.1 Class: CSetupKeywords

```
RobotFramework.Testsuites.Keywords.CSetup
```

Definition setup keywords Method: testsuite\_setup -----

#### 5.1.1 Method: testsuite\_teardown

#### 5.1.2 Method: testcase\_setup

#### 5.1.3 Method: testcase\_teardown

#### 5.1.4 Method: update\_config

### 5.2 Class: CGeneralKeywords

```
RobotFramework.Testsuites.Keywords.CSetup
```

Definition setup keywords Method: get\_config -----

oConfigParams: is the dictionary consist of some configuration params which are return to user from get\_config-params  
keyword Method: load\_json -----



## Chapter 6

# CStruct.py

### 6.1 Class: CStruct

```
RobotFramework.Testsuites.Utils.CStruct
```

Constructor `__init__` creates the given attributes dynamically at runtime.

Args:

Attributes to be created with the initial value

Returns:

Accessible attributes

## Chapter 7

# Event.py

### 7.1 Class: Event

```
RobotFramework.Testsuites.Utils/Events.Event
```

#### 7.1.1 Method: trigger

## Chapter 8

# ScopeEvent.py

### 8.1 Class: ScopeEvent

```
RobotFramework.Testsuites.Utils/Events.ScopeEvent
```

#### 8.1.1 Method: trigger

### 8.2 Class: ScopeStart

```
RobotFramework.Testsuites.Utils/Events.ScopeEvent
```

### 8.3 Class: ScopeEnd

```
RobotFramework.Testsuites.Utils/Events.ScopeEvent
```

## Chapter 9

### `__init__.py`

**9.1**    **Function:** `on`

**9.2**    **Function:** `dispatch`

**9.3**    **Function:** `register_event`

## Chapter 10

# LibListener.py

### 10.1 Class: LibListener

```
RobotFramework.Testsuites.Utills.LibListener
```

Define some hook methods

## Chapter 11

### `__init__.py`

#### 11.1 Class: `RobotFramework.Testsuites`

```
RobotFramework.Testsuites.__init__
```

`RobotFramework.Testsuites` is the Bosch testing library for Robot Framework. `RobotFramework.Testsuites` control peripheral devices, tools and target under testing. Method: `run_keyword` -----

11.1.1 Method: `get_keyword_tags`

11.1.2 Method: `get_keyword_documentation`

11.1.3 Method: `failure_occurred`

#### 11.2 Class: `CTestsuitesCfg`

```
RobotFramework.Testsuites.__init__
```

## Chapter 12

# version.py

### 12.1 Function: robfwaio\_version

Return testsuitemanagement version as Robot framework AIO version

## Chapter 13

# Appendix

About this package:

Table 13.1: Package setup

Setup parameter	Value
Name	RobotFramework.Testsuites
Version	0.2.2
Date	18.07.2022
Description	Functionality to manage RobotFramework testsuites
Package URL	<a href="#">robotframework-testsuitesmanagement</a>
Author	Mai Dinh Nam Son
Email	<a href="mailto:son.maidinhnam@vn.bosch.com">son.maidinhnam@vn.bosch.com</a>
Language	Programming Language :: Python :: 3
License	License :: OSI Approved :: Apache Software License
OS	Operating System :: OS Independent
Python required	>=3.0
Development status	Development Status :: 4 - Beta
Intended audience	Intended Audience :: Developers
Topic	Topic :: Software Development



## Chapter 14

# History

<b>0.1.0</b>	06/2022
<i>Initial version</i>	

---

**RobotFramework.Testsuites.pdf***Created at 17.08.2022 - 14:10:13**by GenPackageDoc v. 0.26.0*

---

## 3.6 QConnectBase

**QConnectBase**

**v. 1.1.0**

Nguyen Huynh Tri Cuong

05.07.2022

# Contents

<b>1</b>	<b>Introduction</b>	<b>1</b>
<b>2</b>	<b>Description</b>	<b>2</b>
<b>3</b>	<b>__init__.py</b>	<b>3</b>
3.1	Class: ConnectionManager . . . . .	3
<b>4</b>	<b>connection_base.py</b>	<b>4</b>
4.1	Class: BrokenConnError . . . . .	4
4.2	Class: ConnectionBase . . . . .	4
4.2.1	Method: is_precondition_pass . . . . .	4
4.2.2	Method: error_instruction . . . . .	4
4.2.3	Method: quit . . . . .	4
4.2.4	Method: connect . . . . .	5
4.2.5	Method: disconnect . . . . .	5
4.2.6	Method: send_obj . . . . .	5
4.2.7	Method: read_obj . . . . .	5
4.2.8	Method: wait_4_trace . . . . .	5
4.2.9	Method: wait_4_trace_continuously . . . . .	5
4.2.10	Method: create_and_activate_trace_queue . . . . .	6
4.2.11	Method: deactivate_and_delete_trace_queue . . . . .	6
4.2.12	Method: activate_trace_queue . . . . .	6
4.2.13	Method: deactivate_trace_queue . . . . .	6
4.2.14	Method: check_timeout . . . . .	6
4.2.15	Method: pre_msg_check . . . . .	7
4.2.16	Method: post_msg_check . . . . .	7
<b>5</b>	<b>connection_manager.py</b>	<b>8</b>
5.1	Class: InputParam . . . . .	8
5.1.1	Method: get_attr_list . . . . .	8
5.2	Class: ConnectParam . . . . .	8
5.2.1	Method: add_connection . . . . .	8
5.2.2	Method: remove_connection . . . . .	9
5.2.3	Method: get_connection_by_name . . . . .	9
5.2.4	Method: disconnect . . . . .	9
5.2.5	Method: connect . . . . .	9
5.2.6	Method: connect_named_args . . . . .	9
5.2.7	Method: connect_unnamed_args . . . . .	9

## CONTENTS

## CONTENTS

5.2.8	Method: <code>send_command</code>	9
5.2.9	Method: <code>send_command_named_args</code>	10
5.2.10	Method: <code>send_command_unnamed_args</code>	10
5.2.11	Method: <code>verify</code>	10
5.2.12	Method: <code>verify_named_args</code>	10
5.2.13	Method: <code>verify_unnamed_args</code>	10
5.3	Class: <code>TestOption</code>	10
<b>6</b>	<b><code>constants.py</code></b>	<b>11</b>
6.1	Class: <code>SocketType</code>	11
6.2	Class: <code>String</code>	11
<b>7</b>	<b><code>qlogger.py</code></b>	<b>12</b>
7.1	Class: <code>ColorFormatter</code>	12
7.2	Class: <code>QFileHandler</code>	12
7.2.1	Method: <code>get_config_supported</code>	12
7.3	Class: <code>QDefaultFileHandler</code>	12
7.3.1	Method: <code>get_config_supported</code>	13
7.4	Class: <code>QConsoleHandler</code>	13
7.5	Class: <code>QLogger</code>	13
7.5.1	Method: <code>set_handler</code>	13
<b>8</b>	<b><code>serial_base.py</code></b>	<b>14</b>
8.1	Class: <code>SerialConfig</code>	14
8.1.1	Method: <code>disconnect</code>	14
8.1.2	Method: <code>quit</code>	14
8.2	Class: <code>SerialClient</code>	14
<b>9</b>	<b><code>raw_tcp.py</code></b>	<b>15</b>
9.1	Class: <code>RawTCPBase</code>	15
<b>10</b>	<b><code>ssh_client.py</code></b>	<b>16</b>
10.1	Class: <code>AuthenticationType</code>	16
10.2	Class: <code>SSHConfig</code>	16
10.2.1	Method: <code>close</code>	16
<b>11</b>	<b><code>tcp_base.py</code></b>	<b>17</b>
11.1	Class: <code>TCPConfig</code>	17
11.1.1	Method: <code>quit</code>	17
11.1.2	Method: <code>connect</code>	17
11.1.3	Method: <code>disconnect</code>	17
11.2	Class: <code>TCPBaseServer</code>	17
11.2.1	Method: <code>connect</code>	18
11.2.2	Method: <code>disconnect</code>	18
11.3	Class: <code>TCPBaseClient</code>	18
11.3.1	Method: <code>disconnect</code>	18
<b>12</b>	<b><code>utils.py</code></b>	<b>19</b>
12.1	Class: <code>Singleton</code>	19

CONTENTS	CONTENTS
12.2 Class: DictToClass . . . . .	19
12.3 Class: Utils . . . . .	19
12.3.1 Method: get_all_sub_classes . . . . .	19
12.3.2 Method: is_valid_host . . . . .	20
12.3.3 Method: execute_command . . . . .	20
12.3.4 Method: kill_process . . . . .	20
12.3.5 Method: caller_name . . . . .	20
12.3.6 Method: load_library . . . . .	20
12.3.7 Method: is_ascii_or_unicode . . . . .	20
12.4 Class: Job . . . . .	20
12.4.1 Method: stop . . . . .	20
12.4.2 Method: run . . . . .	20
12.5 Class: ResultType . . . . .	20
<b>13 Appendix</b>	<b>21</b>
<b>14 History</b>	<b>22</b>

C

# Chapter 1

## Introduction

*QConnectBase*

TO BE CONTINUED

# Chapter 2

## Description

*QConnectBase*  
TO BE CONTINUED

## Chapter 3

### `__init__.py`

#### 3.1 Class: ConnectionManager

```
QConnectBase.__init__
```

Class to manage all connections.



## Chapter 4

# connection\_base.py

### 4.1 Class: BrokenConnError

```
QConnectBase.connection_base
```

### 4.2 Class: ConnectionBase

```
QConnectBase.connection_base
```

Base class for all connection classes. Method: `is_supported_platform` -----  
Check if current platform is supported.

**Returns:** True if platform is supported.  
False if platform is not supported.

#### 4.2.1 Method: `is_precondition_pass`

Check for precondition.

**Returns:** True if passing the precondition.  
False if failing the precondition.

#### 4.2.2 Method: `error_instruction`

Get the error instruction.

**Returns:** Error instruction string.

#### 4.2.3 Method: `quit`

>> This method MUST be overridden in derived class << Abstract method for quitting the connection.

**Args:** `is_disconnect_all`: Determine if it's necessary to disconnect all connections.

**Returns:** None.

**4.2.4 Method: connect**

>> This method MUST be overridden in derived class << Abstract method for quitting the connection.

**Args:** device: Determine if it's necessary to disconnect all connections.

files: Determine if it's necessary to disconnect all connections.

test\_connection: Determine if it's necessary to disconnect all connections.

**Returns:** None.

**4.2.5 Method: disconnect**

>> This method MUST be overridden in derived class << Abstract method for disconnecting connection.

**Args:** device: Device name.

**Returns:** None.

**4.2.6 Method: send\_obj**

Wrapper method to send message to a tcp connection.

**Args:** obj: Data to be sent. cr: Determine if it's necessary to add newline character at the end of command.

**Returns:** None

**4.2.7 Method: read\_obj**

Wrapper method to get the response from connection.

**Returns:** Responded message.

**4.2.8 Method: wait\_4\_trace**

Suspend the control flow until a Trace message is received which matches to a specified regular expression.

**Args:** search\_obj : Regular expression all received trace messages are compare to. Can be passed either as a string or a regular expression object. Refer to Python documentation for module 're'.

use\_fetch\_block : Determine if 'fetch block' feature is used.

end\_of\_block\_pattern : The end of block pattern.

filter\_pattern : Regular expression object to filter message line by line.

timeout : Optional timeout parameter specified as a floating point number in the unit 'seconds'.

fct\_args: Optional list of function arguments passed to be sent.

**Returns:** None : If no trace message matched to the specified regular expression and a timeout occurred.

<match> : If a trace message has matched to the specified regular expression, a match object is returned as the result. The complete trace message can be accessed by the 'string' attribute of the match object. For access to groups within the regular expression, use the group() method. For more information, refer to Python documentation for module 're'.

**4.2.9 Method: wait\_4\_trace\_continuously**

Getting trace log continuously without creating a new trace queue.

**Args:** trace\_queue: Queue to store the traces.

timeout: Timeout for waiting a matched log.

fct\_args: Arguments to be sent to connection.

**Returns:** None : If no trace message matched to the specified regular expression and a timeout occurred.

match object : If a trace message has matched to the specified regular expression, a match object is returned as the result. The complete trace message can be accessed by the 'string' attribute of the match object. For access to groups within the regular expression, use the group() method. For more information, refer to Python documentation for module 're'.

#### 4.2.10 Method: create\_and\_activate\_trace\_queue

Create Queue and assign it to \_trace\_queue object and activate the queue with the search element.

**Args:** search\_element : Regular expression all received trace messages are compare to. Can be passed either as a string or a regular expression object. Refer to Python documentation for module 're'.#

use\_fetch\_block : Determine if 'fetch block' feature is used.

end\_of\_block\_pattern : The end of block pattern.

regex\_line\_filter\_pattern : Regular expression object to filter message line by line.

**Returns:** trq\_handle, trace\_queue: the handle and search object

#### 4.2.11 Method: deactivate\_and\_delete\_trace\_queue

Deactivate trace queue and delete.

**Args:** trq\_handle: Trace queue handle.

trace\_queue: Trace queue object.

**Returns:** None.

#### 4.2.12 Method: activate\_trace\_queue

Activates a trace message filter specified as a regular expression. All matching trace messages are put in the specified queue object.

**Args:** search\_obj : Regular expression all received trace messages are compare to. Can be passed either as a string or a regular expression object. Refer to Python documentation for module 're'.#

trace\_queue : A queue object all trace message which matches the regular expression are put in. The using application must assure, that the queue is emptied or deleted.

use\_fetch\_block : Determine if 'fetch block' feature is used

end\_of\_block\_pattern : The end of block pattern

line\_filter\_pattern : Regular expression object to filter message line by line.

**Returns:** <int> : Handle to deactivate the message filter.

#### 4.2.13 Method: deactivate\_trace\_queue

Deactivates a trace message filter previously activated by ActivateTraceQ() method.

**Args:** handle : Integer object returned by ActivateTraceQ() method.

**Returns:** False : No trace message filter active with the specified handle (i.e. handle is not in use).

True : Trace message filter successfully deleted.

#### 4.2.14 Method: check\_timeout

>> This method will be override in derived class << Check if responded message come in cls.\_RESPOND.TIMEOUT or we will raise a timeout event.

**Args:** msg: Responded message for checking.

**Returns:** None.

**4.2.15 Method: pre\_msg\_check**

>> This method will be override in derived class << Pre-checking message when receiving it from connection.

**Args:** msg: received message to be checked.

**Returns:** None.

**4.2.16 Method: post\_msg\_check**

>> This method will be override in derived class << Post-checking message when receiving it from connection.

**Args:** msg: received message to be checked.

**Returns:** None.

## Chapter 5

# connection\_manager.py

### 5.1 Class: InputParam

```
QConnectBase.connection_manager
```

#### 5.1.1 Method: get\_attr\_list

### 5.2 Class: ConnectParam

```
QConnectBase.connection_manager
```

Class for storing parameters for connect action. Class: SendCommandParam =====

```
QConnectBase.connection_manager
```

Class for storing parameters for send command action. Class: VerifyParam =====

```
QConnectBase.connection_manager
```

Class for storing parameters for verify action. Class: ConnectionManager =====

```
QConnectBase.connection_manager
```

Class to manage all connections. Method: quit -----

Quit connection manager.

**Returns:** None.

#### 5.2.1 Method: add\_connection

Add a connection to managed dictionary.

**Args:** name: connection's name.

conn: connection object.

**Returns:** None.

### 5.2.2 Method: remove\_connection

Remove a connection by name.

**Args:** connection\_name: connection name.

**Returns:** None.

### 5.2.3 Method: get\_connection\_by\_name

Get an exist connection by name.

**Args:** connection\_name: connection's name.

**Returns:** Connection object.

### 5.2.4 Method: disconnect

Keyword for disconnecting a connection by name.

**Args:** connection\_name: Name of connection.

**Returns:** None.

### 5.2.5 Method: connect

Keyword for making a connection.

**Args:** args: Non-Keyword Arguments.

kwargs: Keyword Arguments.

**Returns:** None.

### 5.2.6 Method: connect\_named\_args

Making a connection with name arguments.

**Args:** kwargs: Dictionary of arguments.

**Returns:** None.

### 5.2.7 Method: connect\_unnamed\_args

Making a connection.

**Args:** connection\_name: Name of connection.

connection\_type: Type of connection.

mode: Connection mode.

config: Configuration for connection.

**Returns:** None.

### 5.2.8 Method: send\_command

Keyword for sending command to a connection.

**Args:** args: Non-Keyword Arguments.

kwargs: Keyword Arguments.

**Returns:** None.

**5.2.9 Method: send\_command\_named\_args**

Send command to a connection with name arguments.

**Args:** args: Dictionary of arguments.

**Returns:** None.

**5.2.10 Method: send\_command\_unnamed\_args**

Send command to a connection.

**Args:** connection\_name: connection's name.  
command: command.

**Returns:** None.

**5.2.11 Method: verify**

Keyword uses to verify a pattern from connection response after sending a command.

**Args:** args: Non-Keyword Arguments.  
kwargs: Keyword Arguments.

**Returns:** match\_res: matched string.

**5.2.12 Method: verify\_named\_args**

Verify a pattern from connection response after sending a command with named arguments.

**Args:** kwargs: Dictionary of arguments.

**Returns:** match\_res: matched string.

**5.2.13 Method: verify\_unnamed\_args**

Verify a pattern from connection response after sending a command.

**Args:** connection\_name: connection's name.  
search\_obj: search pattern.  
timeout: timeout for waiting result.  
fetch\_block: use fetch block feature.  
end\_of\_block\_pattern: pattern for detecting the end of block.  
filter\_pattern: line filter pattern.  
fct\_args: command to be sent.

**Returns:** match\_res: matched string.

**5.3 Class: TestOption**

```
QConnectBase.connection_manager
```

## Chapter 6

# constants.py

### 6.1 Class: SocketType

```
QConnectBase.constants
```

### 6.2 Class: String

```
QConnectBase.constants
```



## Chapter 7

# qlogger.py

### 7.1 Class: ColorFormatter

```
QConnectBase.qlogger
```

Custom formatter class for setting log color. Method: format -----

Set the color format for the log.

**Args:** record: log record.

**Returns:** Log with color formatter.

### 7.2 Class: QFileHandler

```
QConnectBase.qlogger
```

Handler class for user defined file in config. Method: get\_log\_path -----

Get the log file path for this handler.

**Args:** config: connection configurations.

**Returns:** Log file path.

#### 7.2.1 Method: get\_config\_supported

Check if the connection config is supported by this handler.

**Args:** config: connection configurations.

**Returns:** True if the config is supported.  
False if the config is not supported.

### 7.3 Class: QDefaultFileHandler

```
QConnectBase.qlogger
```

Handler class for default log file path. Method: get\_log\_path -----

Get the log file path for this handler.

**Args:** logger\_name: name of the logger.

**Returns:** Log file path.

**7.3.1 Method: get\_config\_supported**

Check if the connection config is supported by this handler.

**Args:** config: connection configurations.

**Returns:** True if the config is supported.  
False if the config is not supported.

**7.4 Class: QConsoleHandler**

```
QConnectBase.qlogger
```

Handler class for console log. Method: get\_config\_supported -----  
Check if the connection config is supported by this handler.

**Args:** config: connection configurations.

**Returns:** True if the config is supported.  
False if the config is not supported.

**7.5 Class: QLogger**

```
QConnectBase.qlogger
```

Logger class for QConnect Libraries. Method: get\_logger -----  
Get the logger object.

**Args:** logger\_name: Name of the logger.

**Returns:** Logger object.

**7.5.1 Method: set\_handler**

Set handler for logger.

**Args:** config: connection configurations.

**Returns:** None if no handler is set. Handler object.

## Chapter 8

# serial\_base.py

### 8.1 Class: SerialConfig

```
QConnectBase.serialclient.serial_base
```

Class to store the configuration for Serial connection. Class: SerialSocket =====

```
QConnectBase.serialclient.serial_base
```

Class for handling serial connection. Method: connect -----  
Connect to serial port.

**Returns:** None.

#### 8.1.1 Method: disconnect

Disconnect serial port.

**Args:** \_device: unused.

**Returns:** None.

#### 8.1.2 Method: quit

Quit serial connection.

**Returns:** None

### 8.2 Class: SerialClient

```
QConnectBase.serialclient.serial_base
```

Serial client class. Method: connect -----  
Connect to the Serial port.

**Returns:** None.

## Chapter 9

# raw\_tcp.py

### 9.1 Class: RawTCPBase

```
QConnectBase.tcp/raw.raw_tcp
```

Base class for a raw tcp connection. Class: RawTCPServer =====

```
QConnectBase.tcp/raw.raw_tcp
```

Class for a raw tcp connection server. Class: RawTCPClient =====

```
QConnectBase.tcp/raw.raw_tcp
```

Class for a raw tcp connection client.

## Chapter 10

# ssh\_client.py

### 10.1 Class: AuthenticationType

```
QConnectBase.tcp/ssh.ssh_client
```

### 10.2 Class: SSHConfig

```
QConnectBase.tcp/ssh.ssh_client
```

Class to store the configuration for SSH connection. Class: SSHClient =====

```
QConnectBase.tcp/ssh.ssh_client
```

SSH client connection class. Method: connect -----

Implementation for creating a SSH connection.

**Returns:** None.

#### 10.2.1 Method: close

Close SSH connection.

Returns: Method: quit -----

Quit and stop receiver thread.

**Returns:** None.

## Chapter 11

# tcp\_base.py

### 11.1 Class: TCPConfig

```
QConnectBase.tcp.tcp_base
```

Class to store configurations for TCP connection. Class: TCPBase =====

```
QConnectBase.tcp.tcp_base
```

Base class for a tcp connection. Method: close -----

Close connection.

**Returns:** None.

#### 11.1.1 Method: quit

Quit connection.

**Args:** is\_disconnect\_all: Determine if it's necessary for disconnect all connection.

**Returns:** None.

#### 11.1.2 Method: connect

>> Should be override in derived class. Establish the connection.

**Returns:** None.

#### 11.1.3 Method: disconnect

>> Should be override in derived class. Disconnect the connection.

**Returns:** None.

### 11.2 Class: TCPBaseServer

```
QConnectBase.tcp.tcp_base
```

Base class for TCP server. Method: accept\_connection -----

Wrapper method for handling accept action of TCP Server.

**Returns:** None.

**11.2.1 Method: connect**

**11.2.2 Method: disconnect**

**11.3 Class: TCPBaseClient**

```
QConnectBase.tcp.tcp_base
```

Base class for TCP client. Method: connect -----

**11.3.1 Method: disconnect**

## Chapter 12

# utils.py

### 12.1 Class: Singleton

```
QConnectBase.utils
```

Class to implement Singleton Design Pattern. This class is used to derive the TTFisClientReal as only a single instance of this class is allowed.

Disabled pyLint Messages: R0903: Too few public methods (%s/%s) Used when class has too few public methods, so be sure it's really worth it.

This base class implements the Singleton Design Pattern required for the TTFisClientReal. Adding further methods does not make sense.

### 12.2 Class: DictToClass

```
QConnectBase.utils
```

Class for converting dictionary to class object. Method: validate -----

### 12.3 Class: Utils

```
QConnectBase.utils
```

Class to implement utilities for supporting development. Method: get\_all\_descendant\_classes -----  
---

Get all descendant classes of a class

**Args:** cls: Input class for finding descendants.

**Returns:** Array of descendant classes.

#### 12.3.1 Method: get\_all\_sub\_classes

Get all children classes of a class

**Args:** cls: Input class for finding children.

**Returns:** Array of children classes.



**12.3.2 Method: is\_valid\_host****12.3.3 Method: execute\_command****12.3.4 Method: kill\_process****12.3.5 Method: caller\_name**

Get a name of a caller in the format module.class.method

**Args:** skip: specifies how many levels of stack to skip while getting caller name. skip=1 means "who calls me", skip=2 "who calls my caller" etc.

**Returns:** An empty string is returned if skipped levels exceed stack height

**12.3.6 Method: load\_library**

Load native library depend on the calling convention.

**Args:** path: library path. is\_stdcall: determine if the library's calling convention is stdcall or cdecl.

**Returns:** Loaded library object.

**12.3.7 Method: is\_ascii\_or\_unicode**

Check if the string is ascii or unicode

**Args:** str\_check: string for checking codecs: encoding type list

**Returns:** True : if checked string is ascii or unicode False : if checked string is not ascii or unicode

**12.4 Class: Job**

```
QConnectBase.utils
```

**12.4.1 Method: stop****12.4.2 Method: run****12.5 Class: ResultType**

```
QConnectBase.utils
```

Result Types. Class: ResponseMessage =====

```
QConnectBase.utils
```

Response message class Method: get\_json -----

Convert response message to json Returns: Response message in json format Method: get\_data -----

Get string data result Returns: String result Method: create\_from\_string -----

## Chapter 13

# Appendix

About this package:

Table 13.1: Package setup

Setup parameter	Value
Name	QConnectBase
Version	1.1.0
Date	05.07.2022
Description	Robot Framework test library for TCP, SSH, serial connection
Package URL	<a href="#">robotframework-qconnect-base</a>
Author	Nguyen Huynh Tri Cuong
Email	<a href="mailto:cuong.nguyenhuynhtri@vn.bosch.com">cuong.nguyenhuynhtri@vn.bosch.com</a>
Language	Programming Language :: Python :: 3
License	License :: OSI Approved :: Apache Software License
OS	Operating System :: OS Independent
Python required	>=3.0
Development status	Development Status :: 4 - Beta
Intended audience	Intended Audience :: Developers
Topic	Topic :: Software Development

## Chapter 14

# History

<b>1.0.0</b>	2022
<i>Initial version</i>	

---

**QConnectBase.pdf***Created at 17.08.2022 - 14:10:25**by GenPackageDoc v. 0.26.0*

---

## 3.7 QConnectionDLTLibrary

# QConnectionDLTLibrary

**v. 1.1.0**

Nguyen Huynh Tri Cuong

11.07.2022

# Contents

<b>1</b>	<b>Introduction</b>	<b>1</b>
<b>2</b>	<b>Description</b>	<b>2</b>
<b>3</b>	<b>trace_client.py</b>	<b>3</b>
3.1	Class: TraceClient . . . . .	3
3.1.1	Method: quit . . . . .	3
3.1.2	Method: connect . . . . .	3
3.1.3	Method: select_device . . . . .	3
3.1.4	Method: is_device_connected . . . . .	3
3.1.5	Method: enable_mst_socket . . . . .	4
3.1.6	Method: disconnect . . . . .	4
3.1.7	Method: restart . . . . .	4
3.1.8	Method: create_and_activate_trace_queue . . . . .	4
3.1.9	Method: deactivate_and_delete_trace_queue . . . . .	4
3.1.10	Method: wait_4_trace . . . . .	4
3.1.11	Method: wait_4_trace_continuously . . . . .	4
3.1.12	Method: remove_servers_process . . . . .	4
3.1.13	Method: add_server_process . . . . .	4
3.1.14	Method: supported_devices . . . . .	4
<b>4</b>	<b>trace_client.base.py</b>	<b>5</b>
4.1	Function: wait . . . . .	5
4.2	Class: TraceClientBase . . . . .	5
4.2.1	Method: is_precondition_pass . . . . .	5
4.2.2	Method: error_instruction . . . . .	5
4.2.3	Method: get_selected_device . . . . .	5
4.2.4	Method: quit . . . . .	6
4.2.5	Method: connect . . . . .	6
4.2.6	Method: select_device . . . . .	6
4.2.7	Method: enable_mst_socket . . . . .	6
4.2.8	Method: disconnect . . . . .	6
4.2.9	Method: restart . . . . .	6
4.2.10	Method: get_selected_device . . . . .	6
4.2.11	Method: is_device_connected . . . . .	6
<b>5</b>	<b>dlt_client.py</b>	<b>7</b>
5.1	Class: BrokenConnError . . . . .	7

CONTENTS	CONTENTS
5.2 Class: DLTConfig . . . . .	7
5.3 Class: DLTClient . . . . .	7
5.3.1 Method: error_instruction . . . . .	7
5.3.2 Method: get_selected_device . . . . .	7
5.3.3 Method: enable_mst_socket . . . . .	8
5.3.4 Method: check_timeout . . . . .	8
5.3.5 Method: pre_msg_check . . . . .	8
5.3.6 Method: read_obj . . . . .	8
5.3.7 Method: connect . . . . .	8
5.3.8 Method: quit . . . . .	8
5.3.9 Method: disconnect . . . . .	8
5.3.10 Method: restart . . . . .	8
5.3.11 Method: select_device . . . . .	9
6 Appendix	10
7 History	11

B

# Chapter 1

## Introduction

*QConnectionDLTLibrary*  
TO BE CONTINUED

# Chapter 2

## Description

*QConnectionDLTLibrary*  
TO BE CONTINUED



## Chapter 3

# trace\_client.py

### 3.1 Class: TraceClient

```
QConnectionDLTLibrary.trace/common.trace_client
```

Proxy class for redirect to real trace class. Method: get\_selected\_device -----  
Get the selected device.

**Returns:** The selected device.

#### 3.1.1 Method: quit

Quit connection.

**Args:** disconnect\_all: Determine if it's necessary for disconnect all connection.

**Returns:** None.

#### 3.1.2 Method: connect

Establish the connection.

**Args:** args: Arguments for connecting.

**Returns:** True if connect successfully.  
False if connect unsuccessfully.

#### 3.1.3 Method: select\_device

Select the device.

**Args:** device: Name of the device to be selected.

**Returns:** None.

#### 3.1.4 Method: is\_device\_connected

Check if the device is connected.

**Args:** device: Name of the device.

**Returns:** True if the device is connected.  
False if the device hasn't been connected.

**3.1.5 Method: enable\_mst\_socket**

Not implemented yet.

**Args:** port\_addr: Port address.

**Returns:** None.

**3.1.6 Method: disconnect**

Disconnect the connection.

**Args:** device: Name of the device.

**Returns:** None.

**3.1.7 Method: restart**

Restart the connection.

**Args:** args : Arguments for restarting.

Returns:

True if restarting successfully.

False if restarting unsuccessfully.

**3.1.8 Method: create\_and\_activate\_trace\_queue**

Create Queue and assign it to .trace\_queue object and activate the queue with the search element.

**Args:** search\_element : Regular expression all received trace messages are compare to. Can be passed either as a string or a regular expression object. Refer to Python documentation for module 're'.#

use\_fetch\_block : Determine if 'fetch block' feature is used.

end\_of\_block\_pattern : The end of block pattern.

regex\_line\_filter\_pattern : Regular expression object to filter message line by line.

**Returns:** trq\_handle, trace\_queue : the handle and search object

**3.1.9 Method: deactivate\_and\_delete\_trace\_queue**

Deactivate trace queue and delete.

**Args:** trq\_handle: Trace queue handle.

trace\_queue: Trace queue object.

**Returns:** None.

**3.1.10 Method: wait\_4\_trace****3.1.11 Method: wait\_4\_trace\_continuously****3.1.12 Method: remove\_servers\_process****3.1.13 Method: add\_server\_process****3.1.14 Method: supported\_devices**

## Chapter 4

# trace\_client\_base.py

### 4.1 Function: wait

Suspend the control flow for the specified period of time.

**Args:** time2wait : Time information as an integer value unit : Unit information as a string. Supported units are 'ms', 's', 'min'

**Returns:** None.

### 4.2 Class: TraceClientBase

```
QConnectionDLTLibrary.trace/common.trace_client_base
```

A base class for all DLT trace clients. Method: is\_supported\_platform -----  
Check if this platform is supported by the handle class.

**Returns:** True if the platform is supported.  
False if the platform is not supported.

#### 4.2.1 Method: is\_precondition\_pass

Checking precondition.

**Returns:** True if passing precondition.  
False if failing precondition.

#### 4.2.2 Method: error\_instruction

Get error instruction.

**Returns:** Error instruction string.

#### 4.2.3 Method: get\_selected\_device

Abstract method for getting selected device.

**Returns:** None.

**4.2.4 Method: quit**

Abstract method for quitting connection.

**Args:** `is_disconnect_all`: Determine if it's necessary for disconnecting all connection.

**Returns:** None.

**4.2.5 Method: connect**

Abstract method for connecting.

**Args:** `args`: Arguments for connecting.

**Returns:** None.

**4.2.6 Method: select\_device**

Abstract method for selecting device.

**Args:** `device`: Device name.

**Returns:** None.

**4.2.7 Method: enable\_mst\_socket**

Abstract method for enabling mst socket.

**Args:** `port_addr`: Port address.

**Returns:** None.

**4.2.8 Method: disconnect**

Abstract method for disconnecting connection.

**Args:** `device`: Device name.

**Returns:** None.

**4.2.9 Method: restart**

Abstract method for restarting DLT connection.

**Args:** `args`: Arguments for restarting.

**Returns:** None.

**4.2.10 Method: get\_selected\_device**

This method returns the currently connected and active device. Be aware that the active device might change any time (e.g. by a parallel thread). Method: `is_device_connected` -----

Check if device is connected.

**Args:** `device`: Device to be checked.

**Returns:** True if device is connected.  
False if device is not connected.

**4.2.11 Method: is\_device\_connected**

This method returns True if the device is already connected.

## Chapter 5

# dlt\_client.py

### 5.1 Class: BrokenConnError

```
QConnectionDLTLibrary.trace.dlt_client
```

### 5.2 Class: DLTCConfig

```
QConnectionDLTLibrary.trace.dlt_client
```

Class for storing configurations for DLTConnector. Method: validate -----

### 5.3 Class: DLTClient

```
QConnectionDLTLibrary.trace.dlt_client
```

Class for handling dlt connection via dlt connector. Method: is\_process\_running -----

Check if a process is running.

**Args:** process\_name : Name of the process to be checked.  
cmdline\_check : Check the process' commandline contain.

**Returns:** True : If the process is running.  
False: If the process is not running.

#### 5.3.1 Method: error\_instruction

Get error instruction.

**Returns:** Error instruction.

#### 5.3.2 Method: get\_selected\_device

Get selected device.

**Returns:** Selected device.

**5.3.3 Method: enable\_mst\_socket**

Not implemented.

**Args:** port\_addr:

**Returns:** None.

**5.3.4 Method: check\_timeout**

Check if waiting response timeout exceeded.

**Args:** msg: Message to be checked.

**Returns:** None.

**5.3.5 Method: pre\_msg\_check**

Check for the trace file loaded message.

**Args:** msg: Message to be checked.

**Returns:** None

**5.3.6 Method: read\_obj**

Override read\_obj function for DLTServerApp communication.

**Returns:** Received message from DLTServerApp through TCPIP.

**5.3.7 Method: connect**

Connect to DLTServerApp through socket.

**Args:** test\_connection: determine if connection test is necessary.

**Returns:** Device's name if connecting successfully.

**5.3.8 Method: quit**

Quit DLTCconnector client.

**Args:** disconnect\_all: Determine if all connection will be disconnected.

**Returns:** None.

**5.3.9 Method: disconnect**

Disconnect device.

**Args:** device: device's name

**Returns:** None

**5.3.10 Method: restart**

Restart the connection.

**Args:** files: Trace file list.

**Returns:** True if restart successfully.

False if restart unsuccessfully.

**5.3.11 Method: select\_device**

This method selects an already connected device.

**Args:** device: name of device as a string.

**Returns:** None.

## Chapter 6

# Appendix

About this package:

Table 6.1: Package setup

Setup parameter	Value
Name	QConnectionDLTLibrary
Version	1.1.0
Date	11.07.2022
Description	Robot Framework test library for TCP, SSH, serial connection
Package URL	<a href="#">robotframework-qconnect-dlt</a>
Author	Nguyen Huynh Tri Cuong
Email	<a href="mailto:cuong.nguyenhuynhtri@vn.bosch.com">cuong.nguyenhuynhtri@vn.bosch.com</a>
Language	Programming Language :: Python :: 3
License	License :: OSI Approved :: Apache Software License
OS	Operating System :: OS Independent
Python required	>=3.0
Development status	Development Status :: 4 - Beta
Intended audience	Intended Audience :: Developers
Topic	Topic :: Software Development



# Chapter 7

## History

1.0.0	2022
<i>Initial version</i>	

## 3.8 RobotResults2RQM

# RobotResults2RQM

**v. 1.1.1**

Tran Duy Ngoan

05.07.2022

# Contents

<b>1</b>	<b>Introduction</b>	<b>1</b>
<b>2</b>	<b>Description</b>	<b>2</b>
<b>3</b>	<b>CRQM.py</b>	<b>3</b>
3.1	Function: <code>get_xml_tree</code>	3
3.2	Class: <code>CRQMClient</code>	3
3.2.1	Method: <code>login</code>	3
3.2.2	Method: <code>verifyProjectName</code>	4
3.2.3	Method: <code>disconnect</code>	4
3.2.4	Method: <code>userURL</code>	4
3.2.5	Method: <code>integrationURL</code>	4
3.2.6	Method: <code>webIDfromResponse</code>	5
3.2.7	Method: <code>webIDfromGeneratedID</code>	5
3.2.8	Method: <code>getResourceByID</code>	5
3.2.9	Method: <code>getAllByResource</code>	5
3.2.10	Method: <code>getAllBuildRecords</code>	5
3.2.11	Method: <code>addTeamAreaNode</code>	6
3.2.12	Method: <code>createTestcaseTemplate</code>	6
3.2.13	Method: <code>createTCERTemplate</code>	6
3.2.14	Method: <code>createExecutionResultTemplate</code>	6
3.2.15	Method: <code>createBuildRecordTemplate</code>	7
3.2.16	Method: <code>createConfigurationTemplate</code>	7
3.2.17	Method: <code>createTSERTemplate</code>	7
3.2.18	Method: <code>createTestsuiteResultTemplate</code>	7
3.2.19	Method: <code>createResource</code>	8
3.2.20	Method: <code>createBuildRecord</code>	8
3.2.21	Method: <code>createConfiguration</code>	8
3.2.22	Method: <code>updateResourceByID</code>	8
3.2.23	Method: <code>linkListTestcase2Testplan</code>	8
3.2.24	Method: <code>linkListTestcase2Testsuite</code>	9
<b>4</b>	<b><code>__init__.py</code></b>	<b>10</b>
<b>5</b>	<b><code>robot2rqm.py</code></b>	<b>11</b>
5.1	Function: <code>get_from_tags</code>	11
5.2	Function: <code>convert_to_datetime</code>	11
5.3	Function: <code>process_suite_metadata</code>	11

CONTENTS	CONTENTS
5.4 Function: process_metadata . . . . .	11
5.5 Function: process_suite . . . . .	12
5.6 Function: process_test . . . . .	12
5.7 Function: RobotResults2RQM . . . . .	12
5.8 Class: Logger . . . . .	12
5.8.1 Method: log . . . . .	13
5.8.2 Method: log_warning . . . . .	13
5.8.3 Method: log_error . . . . .	13
6 Appendix	14
7 History	15

B

---

*CHAPTER 1. INTRODUCTION*

---

## Chapter 1

# Introduction

*RobotResults2RQM*

!!! add introduction - if wanted !!

# Chapter 2

## Description

The RobotResults2RQM:  
TO BE CONTINUED

## Chapter 3

# CRQM.py

### 3.1 Function: get\_xml\_tree

Parse xml object from file.

**Args:** file\_name : path to file or file-like object. bdd\_validation : if True, validate against a DTD referenced by the document.

**Returns:** oTree : xml etree object

### 3.2 Class: CRQMClient

```
RobotResults2RQM.CRQM
```

CRQMClient class uses RQM REST APIs to get, create and update resources (testplan, testcase, test result, ...) on RQM - Rational Quality Manager

**Resource type mapping:**

- buildrecord: Build Record
- configuration: Test Environment
- testplan: Test Plan
- testsuite: Test Suite
- suiteexecutionrecord: Test Suite Execution Record (TSER)
- testsuitelog: Test Suite Log
- testcase: Test Case
- executionworkitem: Test Execution Record (TCER)
- executionresult: Execution Result

#### 3.2.1 Method: login

Log in RQM by provided user & password.

**Note:** When the authentication is successful, the JSESSIONID from cookies will be stored as header for later POST method.

**Returns:** True if successful, False otherwise.

### 3.2.2 Method: verifyProjectName

Verify the project name by searching it in project-areas XML response.

**Note: The found project ID will be stored and:**

- required for team-areas request (project name cannot be used)
- used for all later request urls instead of project name

**Returns:**

- True if the authentication is successful.
- False if the authentication is failed.

### 3.2.3 Method: disconnect

Disconnect from RQM Method: config -----

**Configure RQMClient with testplan ID, build, configuration, createmissing, ...**

- Verify the existence of provided testplan ID.
- Verify the existences of provided build and configuration names before creating new ones.

**Args:** plan.id : testplan ID of RQM project for importing result(s).

**build\_name (optional) : the Build Record for linking result(s).** Set it to None if not be used, the empty name " may lead to error.

**config\_name (optional) : the Test Environment for linking result(s).** Set it to None if not be used, the empty name " may lead to error.

**createmissing (optional) : in case this argument is set to True,** the testcase without tcid information will be created on RQM.

**updatetestcase (optional) : in case this argument is set to True,** the information of testcase on RQM will be updated bases on robot testfile.

suite.id (optional) : testsuite ID of RQM project for importing result(s).

**Returns:** None.

### 3.2.4 Method: userURL

Return interaction URL of provided userID

**Args:** userID : the user ID

**Returns:** userURL : the interaction URL of provided userID

### 3.2.5 Method: integrationURL

Return interaction URL of provided resource and ID.

**Note:** ID can be internalID (contains only digits) or externalID.

**Args:** resourceType : the RQM resource type (e.g: "testplan", "testcase", ...)

**id (optional) : ID of given resource.** If given: the specified url to resource ID is returned. If 'None': the url to resource type (to get all entity) is returned.

forceinternalID (optional) : force to return the url of resource as internal ID.

**Returns:** integrationURL : interaction URL of provided resource and ID.



**3.2.6 Method: webIDfromResponse**

Get internal ID (number) from response of POST method.

**Note:** Only executionresult has response text. Other resources has only response header.

**Args:** response : the response from POST method.  
tagID : tag name which contains ID information.

**Returns:** resultId : internal ID (as number).

**3.2.7 Method: webIDfromGeneratedID**

Return web ID (ns2:webId) from generate ID by get resource data from RQM.

**Note:**

- This method is only used for generated testcase, executionworkitem and executionresult.
- buildrecord and configuration does not have ns2:webId in response data.

**Args:** resourceType : the RQM resource type.  
generateID : the Slug ID which is returned in Content-Location from POST response.

**Returns:** webID : web ID (number).

**3.2.8 Method: getResourceByID**

Return data of provided resource and ID by GET method

**Args:** resourceType : the RQM resource type.  
id : ID of resource.

**Returns:** res : response data of GET request.

**3.2.9 Method: getAllByResource**

Return all entries of provided resource by GET method.

**Note:** This method will try to fetch all entries in all pages of resource.

**Args:** resourceType : the RQM resource type.

**Returns:** dReturn : a dictionary which contains response status, message and data.

**3.2.10 Method: getAllBuildRecords**

Get all available build records of project on RQM and store them into dBuildVersion property. Method: getAllConfigurations -----

Get all available configurations of project on RQM and store them into dConfiguration property. Method: getAllTeamAreas -----

Get all available team-areas of project on RQM and store them into dTeamAreas property.

**Example:** { 'teamA' : '{host}/qm/process/project-areas/{project-id}/team-areas/{teamA-id}', 'teamB' : '{host}/qm/process/project-areas/{project-id}/team-areas/{teamB-id} }

**3.2.11 Method: addTeamAreaNode**

Append team-area node which contains URL to given team-area into xml template

**Note:** team-area information is case-casesensitive

**Args:** root : xml root object.

sTeam : team name to be added.

**Returns:** root : xml root object with addition team-area node.

**3.2.12 Method: createTestcaseTemplate**

Return testcase template from provided information.

**Args:** testcaseName : testcase name.

sDescription (optional) : testcase description.

sComponent (optional) : component which testcase is belong to.

sFID (optional) : function ID(requirement ID) for linking.

sTeam (optional) : team name for linking.

sRobotFile (optional) : link to robot file on source control.

sTestType (optional) : test type information.

sASIL (optional) : ASIL information.

sOwnerID (optional) : user ID of testcase owner.

sTCtemplate (optional) : existing testcase template as xml string. If not provided, template file under *RQM\_templates* is used as default.

**Returns:** xml template as string.

**3.2.13 Method: createTCERTemplate**

Return testcase execution record template from provided information

**Args:** testcaseID : testcase ID.

testcaseName : testcase name.

testplanID : testplan ID for linking.

confID (optional) : configuration - Test Environment for linking.

sTeam (optional) : team name for linking.

sOwnerID (optional) : user ID of testcase owner.

**Returns:** xml template as string.

**3.2.14 Method: createExecutionResultTemplate**

Return testcase execution result template from provided information

**Args:** testcaseID : testcase ID.

testcaseName : testcase name.

testplanID : testplan ID for linking.

TCERID : testcase execution record (TCER) ID for linking.

resultState : testcase result status.

startTime : testcase start time.

endTime (optional) : testcase end time.

duration (optional) : testcase duration.

testPC (optional) : test PC which executed testcase.  
 testBy (optional) : user ID who executed testcase.  
 lastlog (optional) : traceback information (for Failed testcase).  
 buildrecordID (optional) : Build Record ID for linking.  
 sTeam (optional) : team name for linking.  
 sOwnerID (optional) : user ID of testcase owner.

**Returns:** xml template as string.

### 3.2.15 Method: createBuildRecordTemplate

Return build record template from provided build name

**Args:** buildName : Build Record name.

**Returns:** xml template as string.

### 3.2.16 Method: createConfigurationTemplate

Return configuration - Test Environment template from provided configuration name

**Args:** buildName : configuration - Test Environment name.

**Returns:** xml template as string.

### 3.2.17 Method: createTSERTemplate

Return testsuite execution record (TSER) template from provided configuration name

**Args:** testsuiteID : testsuite ID.

testsuiteName : testsuite name.

testplanID : testplan ID for linking.

confID (optional) : configuration - Test Environment ID for linking.

sOwnerID (optional) : user ID of testsuite owner.

**Returns:** xml template as string.

### 3.2.18 Method: createTestsuiteResultTemplate

Return testsuite execution result template from provided configuration name

**Args:** testsuiteID : testsuite ID.

testsuiteName : testsuite name.

TSERID : testsuite execution record (TSER) ID for linking.

ITCER : list of testcase execution records (TCER) for linking.

ITCResults : list of testcase results for linking.

startTime (optional) : testsuite start time.

endTime (optional) : testsuite end time.

duration (optional) : testsuite duration.

sOwnerID (optional) : user ID of testsuite owner.

**Returns:** xml template as string.

**3.2.19 Method: createResource**

Create new resource with provided data from template by POST method.

**Args:** resourceType : resource type.  
content: xml template as string.

**Returns:** returnObj: a response dictionary which contains status, ID, status\_code and error message.  
{ 'success' : False, 'id': None, 'message': ", 'status\_code': " }

**3.2.20 Method: createBuildRecord**

Create new build record.

**Note:** Tool will check if build record is already existing or not (both on RQM and current execution).

**Args:** sBuildSWVersion : build version - Build Record name.  
forceCreate (optional) : if True, force to create new build record without existing verification.

**Returns:** returnObj: a response dictionary which contains status, ID, status\_code and error message.  
{ 'success' : False, 'id': None, 'message': ", 'status\_code': " }.

**3.2.21 Method: createConfiguration**

Create new configuration - test environment.

**Note:** Tool will check if configuration is already existing or not (both on RQM and current execution).

**Args:** sConfigurationName : configuration - Test Environment name.  
forceCreate (optional) : if True, force to create new Test Environment without existing verification.

**Returns:** returnObj: a response dictionary which contains status, ID, status\_code and error message.  
{ 'success' : False, 'id': None, 'message': ", 'status\_code': " }

**3.2.22 Method: updateResourceByID**

Update data of provided resource and ID by PUT method.

**Args:** resourceType : resource type.  
id : resource id.  
content : xml template as string.

**Returns:** res : response object from PUT request.

**3.2.23 Method: linkListTestcase2Testplan**

Link list of test cases to provided testplan ID.

**Args:** testplanID : testplan ID to link given testcase(s).

**lTestcases** : list of testcase(s) to be linked with given testplan. If None (as default), lTestcaseIDs property will be used as list of testcase.

**Returns:** res : response object which contains status and error message. { 'success' : False, 'message': " }

**3.2.24 Method: linkListTestcase2Testsuite**

Link list of test cases to provided testsuite ID

**Args:** testsuiteID : testsuite ID to link given testcase(s).

**lTestcases : list of testcase(s) to be linked with given testsuite.** If None (as default), lTestcaseIDs property will be used as list of testcase.

**Returns:** res : response object which contains status and error message. { 'success' : False, 'message': '' }

## Chapter 4

### `__init__.py`

RobotResults2RQM package provides an interface to import robot result(s) from output.xml result file to IBM Rational Quality Manager (RQM).

## Chapter 5

# robot2rqm.py

### 5.1 Function: get\_from\_tags

Extract testcase information from tags.

**Example:** TCID-xxxx, FID-xxxx, ...

**Args:** lTags : list of tag information.

reInfo : regex to get the expected info (ID) from tag info.

**Returns:** lInfo : list of expected information (ID)

### 5.2 Function: convert\_to\_datetime

Convert time string to datetime.

**Args:** time : string of time.

**Returns:** dt : datetime object

### 5.3 Function: process\_suite\_metadata

Try to find metadata information from all suite levels.

**Note:** Metadata at top suite level has a highest priority.

**Args:** suite : Robot suite object.

default\_metadata: initial Metadata information for updating.

**Returns:** dMetadata : dictionary of Metadata information.

### 5.4 Function: process\_metadata

Extract metadata from suite result bases on DEFAULT\_METADATA

**Args:** metadata : Robot metadata object.

default\_metadata: initial Metadata information for updating.

**Returns:** dMetadata : dictionary of Metadata information.

## 5.5 Function: process\_suite

process robot suite for importing to RQM.

**Args:** RQMClient : RQMClient object.

suite : Robot suite object.

**Returns:** None.

## 5.6 Function: process\_test

process robot test for importing to RQM.

**Args:** RQMClient : RQMClient object.

test : Robot test object.

**Returns:** None.

## 5.7 Function: RobotResults2RQM

Import robot results from output.xml to RQM - IBM Rational Quality Manager.

**Flow to import Robot results to RQM:**

1. Process provided arguments from command line
2. Login Rational Quality Management (RQM)
3. Parse Robot results
4. Import results into RQM
5. Link all executed testcases to provided testplan/testsuite ID

**Args: args : Argument parser object:**

- outputfile : path to the output file or directory with output files to be imported.
- host : RQM host url.
- project : RQM project name.
- user : user for RQM login.
- password : user password for RQM login.
- testplan : RQM testplan ID.
- recursive : if True, then the path is searched recursively for log files to be imported.
- createtesting : if True, then all testcases without fcid are created when importing.
- updatetestcase : if True, then testcases information on RQM will be updated bases on robot testfile.
- dryrun : if True, then just check the RQM authentication and show what would be done.

**Returns:** None.

## 5.8 Class: Logger

```
RobotResults2RQM.robot2rqm
```

Logger class for logging message. Method: config -----

Configure Logger class.

**Args:** output\_console : write message to console output.

output\_logfile : path to log file output.

indent : offset indent.

dryrun : if set, a prefix as 'dryrun' is added for all messages.

**Returns:** None.



### 5.8.1 Method: log

Write log message to console/file output.

**Args:** msg : message to write to output.  
color : color style for the message.  
indent : offset indent.

**Returns:** None.

### 5.8.2 Method: log\_warning

Write warning message to console/file output.

**Args:** msg : message to write to output.

**Returns:** None.

### 5.8.3 Method: log\_error

Write error message to console/file output.

**Args:** msg : message to write to output.  
fatal\_error : if set, tool will terminate after logging error message.

**Returns:** None.

## Chapter 6

# Appendix

About this package:

Table 6.1: Package setup

Setup parameter	Value
Name	RobotResults2RQM
Version	1.1.1
Date	05.07.2022
Description	Imports robot result(s) to IBM Rational Quality Manager (RQM)
Package URL	<a href="#">robotframework-testresult2rqmtool</a>
Author	Tran Duy Ngoan
Email	<a href="mailto:Ngoan.TranDuy@vn.bosch.com">Ngoan.TranDuy@vn.bosch.com</a>
Language	Programming Language :: Python :: 3
License	License :: OSI Approved :: Apache Software License
OS	Operating System :: OS Independent
Python required	>=3.0
Development status	Development Status :: 4 - Beta
Intended audience	Intended Audience :: Developers
Topic	Topic :: Software Development

## Chapter 7

# History

<b>0.1.0</b>	07/2022
<i>Initial version</i>	

---

**RobotResults2RQM.pdf***Created at 17.08.2022 - 14:10:47**by GenPackageDoc v. 0.26.0*

---

## 3.9 RobotResults2DB

# RobotResults2DB

**v. 1.2.1**

Tran Duy Ngoan

05.07.2022

## CONTENTS

## CONTENTS

# Contents

<b>1</b>	<b>Introduction</b>	<b>1</b>
<b>2</b>	<b>Description</b>	<b>2</b>
<b>3</b>	<b>CDataBase.py</b>	<b>3</b>
3.1	Class: CDataBase . . . . .	3
3.1.1	Method: disconnect . . . . .	3
3.1.2	Method: nCreateNewFile . . . . .	4
3.1.3	Method: vCreateNewHeader . . . . .	4
3.1.4	Method: nCreateNewSingleTestCase . . . . .	5
3.1.5	Method: nCreateNewTestCase . . . . .	5
3.1.6	Method: vCreateTags . . . . .	5
3.1.7	Method: vSetCategory . . . . .	6
3.1.8	Method: vUpdateStartEndTime . . . . .	6
3.1.9	Method: arGetCategories . . . . .	6
3.1.10	Method: vCreateAbortReason . . . . .	6
3.1.11	Method: vCreateReanimation . . . . .	6
3.1.12	Method: vCreateCCRdata . . . . .	6
3.1.13	Method: vFinishTestResult . . . . .	6
3.1.14	Method: vUpdateEvtbls . . . . .	7
3.1.15	Method: vUpdateFileEndTime . . . . .	7
3.1.16	Method: vUpdateResultEndTime . . . . .	7
3.1.17	Method: bExistingResultID . . . . .	7
<b>4</b>	<b>__init__.py</b>	<b>8</b>
<b>5</b>	<b>robot2db.py</b>	<b>9</b>
5.1	Function: is_valid_uuid . . . . .	9
5.2	Function: get_from_tags . . . . .	9
5.3	Function: get_branch_from_swversion . . . . .	9
5.4	Function: format_time . . . . .	9
5.5	Function: process_suite_metadata . . . . .	10
5.6	Function: process_metadata . . . . .	10
5.7	Function: process_suite . . . . .	10
5.8	Function: process_test . . . . .	10
5.9	Function: process_config_file . . . . .	10
5.10	Function: validate_config . . . . .	11
5.11	Function: normailze_path . . . . .	11

CONTENTS	CONTENTS
5.12 Function: <code>truncate_string</code> . . . . .	11
5.13 Function: <code>RobotResults2DB</code> . . . . .	12
5.14 Class: <code>Logger</code> . . . . .	12
5.14.1 Method: <code>log</code> . . . . .	12
5.14.2 Method: <code>log_warning</code> . . . . .	12
5.14.3 Method: <code>log_error</code> . . . . .	13
<b>6 Appendix</b>	<b>14</b>
<b>7 History</b>	<b>15</b>
<hr/>	
B	

# Chapter 1

## Introduction

*RobotResults2DB*

!!! add introduction !!

# Chapter 2

## Description

The RobotResults2DB:  
TO BE CONTINUED



## Chapter 3

# CDataBase.py

### 3.1 Class: CDataBase

RobotResults2DB.CDataBase

CDataBase class play a role as mysqlclient and provide methods to interact with TestResultWebApp's database.  
Method: connect -----

Connect to the database with provided authentication and db info.

**Args:** host: URL which is hosted the TestResultWebApp's database.

user : user name for database authentication.

passwd : user password for database authentication.

database : database name.

charset (optional): the connection character set.

**use\_unicode (optional):** If True, CHAR and VARCHAR and TEXT columns are returned as Uni-code strings, using the configured character set.

**Returns:** None.

#### 3.1.1 Method: disconnect

Disconnect from TestResultWebApp's database. Method: cleanAllTables -----

Delete all table data. Please be careful before calling this method. Method: sCreateNewTestResult -----  
-----

Creates a new test result in tbl\_result. This is the main table which is linked to all other data by means of test\_result\_id.

**Args:** \_tbl\_prj\_project : project information.

\_tbl\_prj\_variant : variant information.

\_tbl\_prj\_branch : branch information.

\_tbl\_test\_result\_id : UUID of test result.

\_tbl\_result\_interpretation : result interpretation.

\_tbl\_result\_time\_start : test result start time.

\_tbl\_result\_time\_end : test result end time.

\_tbl\_result\_version\_sw\_target : software version information.

\_tbl\_result\_version\_sw\_test : test version information.

\_tbl\_result\_version\_target : hardware version information.

\_tbl\_result\_jenkinsurl : jenkinsurl in case test result is executed by jenkins.

\_tbl\_result\_reporting\_qualitygate : qualitygate information for reporting.

**Returns:** \_tbl\_test\_result\_id: test\_result\_id.

### 3.1.2 Method: nCreateNewFile

Create new file entry in tbl\_file table.

**Args:** `tbl_file.name` : file name information.

`tbl_file.testers.account` : tester account information.

`tbl_file.testers.machine` : test machine information.

`tbl_file.time.start` : test file start time.

`tbl_file.time.end` : test file end time.

`tbl_test_result.id` : UUID of test result for linking to tbl\_result table.

`tbl_file.origin` : **origin (test framework) of test file.** Deafult is "ROBFW"

**Returns:** `insertedID`: ID of new entry.

### 3.1.3 Method: vCreateNewHeader

Create a new header entry in tbl\_file\_header table which is linked with the file.

**Args:** `tbl_file.id` : file ID information.

`tbl_header.testtoolconfiguration.testtoolname` : test tool name.

`tbl_header.testtoolconfiguration.testtoolversionstring` : test tool version.

`tbl_header.testtoolconfiguration.projectname` : project name.

`tbl_header.testtoolconfiguration.logfileencoding` : encoding of logfile.

`tbl_header.testtoolconfiguration.pythonversion` : Python version info.

`tbl_header.testtoolconfiguration.testfile` : test file name.

`tbl_header.testtoolconfiguration.logfilepath` : path to log file.

`tbl_header.testtoolconfiguration.logfilemode` : mode of log file.

`tbl_header.testtoolconfiguration.ctrlfilepath` : path to control file.

`tbl_header.testtoolconfiguration.configfile` : path to configuration file.

`tbl_header.testtoolconfiguration.confname` : configuration name.

`tbl_header.testfileheader.author` : file author.

`tbl_header.testfileheader.project` : project information.

`tbl_header.testfileheader.testfiledate` : file creation date.

`tbl_header.testfileheader.version.major` : file major version.

`tbl_header.testfileheader.version.minor` : file minor version.

`tbl_header.testfileheader.version.patch` : file patch version.

`tbl_header.testfileheader.keyword` : file keyword.

`tbl_header.testfileheader.shortdescription` : file short description.

`tbl_header.testexecution.useraccount` : tester account who run the execution.

`tbl_header.testexecution.computername` : machine name which is executed on.

`tbl_header.testrequirements.documentmanagement` : requirement management information.

`tbl_header.testrequirements.testenvironment` : requirement environment information.

`tbl_header.testbenchconfig.name` : testbench configuration name.

`tbl_header.testbenchconfig.data` : testbench configuration data.

`tbl_header.preprocessor.filter` : preprocessor filter information.

`tbl_header.preprocessor.parameters` : preprocessor parameters definition.

**Returns:** None.

### 3.1.4 Method: nCreateNewSingleTestCase

Create single testcase entry in tbl\_case table immediately.

**Args:** `_tbl_case_name` : test case name.

`_tbl_case_issue` : test case issue ID.

`_tbl_case_tcid` : test case ID (used for testmanagement tool).

`_tbl_case_fid` : test case requirement (function) ID.

`_tbl_case_testnumber` : order of test case in file.

`_tbl_case_repeatcount` : test case repeatition count.

`_tbl_case_component` : component which test case is belong to.

`_tbl_case_time.start` : test case start time.

`_tbl_case_result_main` : test case main result.

`_tbl_case_result_state` : test case completion state.

`_tbl_case_result_return` : test case result code (as integer).

`_tbl_case_counter_resets` : counter of target reset within test case execution.

`_tbl_case_lastlog` : traceback information when test case is failed.

`_tbl_test_result_id` : UUID of test result for linking to file in tbl\_result table.

`_tbl_file.id` : test file ID for linking to file in tbl\_file table.

**Returns:** `iInsertedID`: ID of new entry.

### 3.1.5 Method: nCreateNewTestCase

Create bulk of test case entries: new test case are buffered and inserted as bulk.

Once `_NUM_BUFFERD_ELEMENTS_FOR_EXECUTEMANY` is reached, the creation query is executed.

**Args:** `_tbl_case_name` : test case name.

`_tbl_case_issue` : test case issue ID.

`_tbl_case_tcid` : test case ID (used for testmanagement tool).

`_tbl_case_fid` : test case requirement (function) ID.

`_tbl_case_testnumber` : order of test case in file.

`_tbl_case_repeatcount` : test case repeatition count.

`_tbl_case_component` : component which test case is belong to.

`_tbl_case_time.start` : test case start time.

`_tbl_case_result_main` : test case main result.

`_tbl_case_result_state` : test case completion state.

`_tbl_case_result_return` : test case result code (as integer).

`_tbl_case_counter_resets` : counter of target reset within test case execution.

`_tbl_case_lastlog` : traceback information when test case is failed.

`_tbl_test_result_id` : UUID of test result for linking to file in tbl\_result table.

`_tbl_file.id` : test file ID for linking to file in tbl\_file table.

**Returns:** None.

### 3.1.6 Method: vCreateTags

Create tag entries.

**Args:** `_tbl_test_result_id` : UUID of test result.

`_tbl_usr_result_tags` : user tags information.

**Returns:** None.

**3.1.7 Method: vSetCategory**

Create category entry.

**Args:** `_tbl_test_result_id` : UUID of test result.  
`_tbl_result_category_main` : category information.

**Returns:** None.

**3.1.8 Method: vUpdateStartTime**

Create start-end time entry.

**Args:** `_tbl_test_result_id` : UUID of test result.  
`_tbl_result_time_start` : result start time.  
`_tbl_result_time_end` : result end time.

**Returns:** None.

**3.1.9 Method: arGetCategories**

Get existing categories.

**Returns:** `arCategories` : list of existing categories.

**3.1.10 Method: vCreateAbortReason**

Create abort reason entry.

**Args:** `_tbl_test_result_id` : UUID of test result.  
`_tbl_abort_reason` : abort reason.  
`_tbl_abort_message` : detail message of abort.

**Returns:** None.

**3.1.11 Method: vCreateReanimation**

Create reanimation entry.

**Args:** `_tbl_test_result_id` : UUID of test result.  
`_tbl_num_of_reanimation` : counter of target reanimation during execution.

**Returns:** None.

**3.1.12 Method: vCreateCCRdata**

Create CCR data per test case.

**Args:** `_tbl_test_case_id` : test case ID.  
`lCCRdata` : list of CCR data.

**Returns:** None.

**3.1.13 Method: vFinishTestResult**

**Finish upload:**

- First do bulk insert of rest of test cases if buffer is not empty.
- Then set state to "new report".

**3.1.14 Method: vUpdateEvtbls**

Call update\_evtbls stored procedure. Method: vUpdateEvtbl -----

Call update\_evtbl stored procedure to update provided test\_result\_id. Method: vEnableForeignKeyCheck -----

Switch foreign\_key\_checks flag. Method: sGetLatestFileID -----

Get latest file ID from tbl.file table.

**Args:** sResultID : UUID of test result to get the latest file ID.

**Returns:** sFileID : file ID.

**3.1.15 Method: vUpdateFileEndTime**

Update test file end time.

**Args:** sFileID : file ID to be updated.

sEndtime : end time information.

**Returns:** None.

**3.1.16 Method: vUpdateResultEndTime**

Update test result end time.

**Args:** sResultID : test result UUID to be updated.

sEndtime : end time information.

**Returns:** None.

**3.1.17 Method: bExistingResultID**

Verify the given test result UUID is existing in tbl.result table or not.

**Args:** sResultID : test result UUID to be verified.

**Returns:** bExisting : True if test result UUID is already existing.

## Chapter 4

### `__init__.py`

RobotResults2DB package provides an interface to import robot result(s) from output.xml result file to TestResultWebApp database.

TestResultWebApp is available in Github as below repo: <https://github.com/test-fullautomation/TestResultWebApp>

## Chapter 5

# robot2db.py

### 5.1 Function: `is_valid_uuid`

Verify the given UUID is valid or not.

**Args:** `uuid_to_test` : UUID to be verified.  
`version (optional)`: UUID version.

**Returns:** True if the given UUID is valid.

### 5.2 Function: `get_from_tags`

Extract testcase information from tags.

**Example:** TCID-xxxx, FID-xxxx, ...

**Args:** `lTags` : list of tag information.  
`reInfo` : regex to get the expected info (ID) from tag info.

**Returns:** `lInfo` : list of expected information (ID)

### 5.3 Function: `get_branch_from_swversion`

Get branch name from software version information.

**Convention of branch information in suffix of software version:**

- All software version with .0F is the main/freature branch. The leading number is the current year. E.g. 17.0F03
- All software version with .1S, .2S, ... is a stabi branch. The leading number is the year of branching out for stabilization. The number before "S" is the order of branching out in the year.

**Args:** `sw_version` : software version.

**Returns:** `branch_name` : branch name.

### 5.4 Function: `format_time`

Format the given time string to TestResultWebApp's format for importing to db.

**Args:** `stime` : string of time.

**Returns:** TestResultWebApp's time format.

## 5.5 Function: process\_suite\_metadata

Try to find metadata information from all suite levels.

**Note:** Metadata at top suite level has a highest priority.

**Args:** suite : Robot suite object.

default\_metadata: initial Metadata information for updating.

**Returns:** dMetadata : dictionary of Metadata information.

## 5.6 Function: process\_metadata

Extract metadata from suite result bases on DEFAULT\_METADATA

**Args:** metadata : Robot metadata object.

default\_metadata: initial Metadata information for updating.

**Returns:** dMetadata : dictionary of Metadata information.

## 5.7 Function: process\_suite

**Process to the lowest suite level (test file):**

- Create new file and its header information
- Then, process all child test cases

**Args:** suite : Robot suite object.

\_tbl\_test\_result\_id : UUID of test result for importing.

root\_metadata : metadata information.

dConfig: configuration data which is parsed from given json configuration file.

**Returns:** None.

## 5.8 Function: process\_test

Process test case data and create new test case record.

**Args:** db : database object.

test : Robot test object.

file\_id : file ID for mapping.

test\_result\_id : test result ID for mapping.

metadata\_info : metadata information.

test\_number : order of test case in file.

**Returns:** None.

## 5.9 Function: process\_config\_file

**Parse information from configuration file:**

- 'component': :



```

    {
        "component" : {
            "componentA" : "componentA/path/to/testcase",
            "componentB" : "componentB/path/to/testcase",
            "componentC" : [
                "componentC1/path/to/testcase",
                "componentC2/path/to/testcase"
            ]
        }
    }
    Then all testcase which its path contain componentA/path/to/testcase
    will be belong to componentA, ...

```

- variant, 'version\_sw': configuration file has low priority than command line

**Args:** config\_file : path to configuration file.

**Returns:** dConfig : configuration object.

## 5.10 Function: validate\_config

Validate the json configuration base on given schema.

Default schema just supports "component", "variant" and "version\_sw" :

```

CONFIG_SCHEMA = {
    "component" : [str, dict],
    "variant"    : str,
    "version_sw" : str,
}

```

**Args:** dConfig : json configuration object to be verified.

sSchema (optional): schema for the validation. CONFIG\_SCHEMA is used as default.

bExitOnFail (optional): If True, exit tool in case the validation is fail.

**Returns:** bValid : True if the given json configuration data is valid.

## 5.11 Function: normailze\_path

Normalize path file.

**Args:** sPath : string of path file to be normalized.

**Returns:** sNPath : string of normalized path file.

## 5.12 Function: truncate\_string

Truncate input string before importing to database.

**Args:** sString : input string for truncation.

iMaxLength : max length of string to be allowed.

sEndChars (optional): end characters which are added to end of truncated string.

**Returns:** content : string after truncation.

## 5.13 Function: RobotResults2DB

Import robot results from output.xml to TestResultWebApp's database

**Flow to import Robot results to database:**

1. Process provided arguments from command line
2. Connect to database
3. Parse Robot results
4. Import results into database
5. Disconnect from database

**Args: args : Argument parser object:**

- outfile : path to the output file or directory with output files to be imported.
- server : server which hosts the database (IP or URL).
- user : user for database login.
- password : password for database login.
- database : database name.
- recursive : if True, then the path is searched recursively for log files to be imported.
- dryrun : if True, then just check the RQM authentication and show what would be done.
- UUID : UUID used to identify the import and version ID on TestResultWebApp.
- variant : variant name to be set for this import.
- versions : metadata: Versions (Software;Hardware;Test) to be set for this import.
- config : configuration json file for component mapping information.

**Returns:** None.

## 5.14 Class: Logger

```
RobotResults2DB.robot2db
```

Logger class for logging message Method: config -----

Configure Logger class.

**Args:** output\_console : write message to console output.

output\_logfile : path to log file output.

indent : offset indent.

dryrun : if set, a prefix as 'dryrun' is added for all messages.

**Returns:** None.

### 5.14.1 Method: log

Write log message to console/file output.

**Args:** msg : message to write to output.

color : color style for the message.

indent : offset indent.

**Returns:** None.

### 5.14.2 Method: log\_warning

Write warning message to console/file output.

**Args:** msg : message to write to output.

**Returns:** None.

### 5.14.3 Method: log\_error

Write error message to console/file output.

**Args:** msg : message to write to output.

fatal\_error : if set, tool will terminate after logging error message.

**Returns:** None.

## Chapter 6

# Appendix

About this package:

Table 6.1: Package setup

Setup parameter	Value
Name	RobotResults2DB
Version	1.2.1
Date	05.07.2022
Description	Imports robot result(s) to TestResultWebApp database
Package URL	<a href="#">robotframework-testresultwebapptool</a>
Author	Tran Duy Ngoan
Email	<a href="mailto:Ngoan.TranDuy@vn.bosch.com">Ngoan.TranDuy@vn.bosch.com</a>
Language	Programming Language :: Python :: 3
License	License :: OSI Approved :: Apache Software License
OS	Operating System :: OS Independent
Python required	>=3.0
Development status	Development Status :: 4 - Beta
Intended audience	Intended Audience :: Developers
Topic	Topic :: Software Development

## Chapter 7

# History

<b>0.1.0</b>	07/2022
<i>Initial version</i>	

---

**RobotResults2DB.pdf***Created at 17.08.2022 - 14:10:58**by GenPackageDoc v. 0.26.0*

---

## 3.10 TestResultWebApp

# TestResultWebApp

**v. 0.1.0**

Thomas Pollerspöck

04.07.2022

CONTENTS		CONTENTS
<h1>Contents</h1>		
1	Introduction	1
1.1	Impressions . . . . .	2
2	Description	6
3	Appendix	7
4	History	8
<hr/>		
A		

# Chapter 1

## Introduction

This package provides a generic web based open source application which allows processing displaying of test result data in a sophisticated way.

### **TO BE CONTINUED**


(Place the content of

HowTo\_curl\_test\_TODO\_convertto\_rst.txt and

HowTo\_NewWebApp\_instance\_TODO\_convertto\_rst.txt here)



## 1.1 Impressions





The screenshot displays the CMD BVT Dashboard interface. The top navigation bar includes a search bar, user profile, and various filters. The left sidebar contains links to Dashboard, Data table, Run-time view, Links, and CMD Bug Tracking. The main content area shows a table titled "CMD BVT - data table" with columns for Result, Name, Component, and tcid. The table lists several test cases, mostly related to audio components like AUX\_2, TUNER\_AM, and TUNER\_FM. A detailed view of a test case is shown, including a comment from Ashok dated 11.04.17 and a comment from Manohara dated 21.12.17. The dashboard also shows a summary of test results: (QG 00% not passed, Worst comp.: Reception/Dab 74% passed).

Result	Name	Component	tcid
INVALID sink connection	Tests/testcases/connect/UTS_02_027.tml	Audio	TC1459
Connected to AUX_2	Tests/testcases/connect/UTS_02_028.tml	Audio	TC1412
change source from AUX_2 to TUNER_AM and sink internal Amp	Tests/testcases/connect/UTS_02_030.tml	Audio	TC1460
change source from AUX_2 to TUNER_FM and sink internal Amp	Tests/testcases/connect/UTS_02_032.tml	Audio	TC1415
change source from AUX_2 to MEDIA_PLAYER and sink internal Amp	Tests/testcases/connect/UTS_02_037.tml	Audio	TC1421
change source from AUX_2 to AUX_2 and sink internal Amp	Tests/testcases/connect/UTS_02_053.tml	Audio	TC3005
INVALID sink connection	Tests/testcases/connect/UTS_02_054.tml	Audio	TC1440
Connect to TUNER_AM	Tests/testcases/connect/UTS_02_059.tml	Audio	TC1463
change source from TUNER_AM to TUNER_FM and sink internal Amp	Tests/testcases/connect/UTS_02_064.tml	Audio	TC1483

Comments for TC1415:

- 11.04.17 13:34 Ashok: The RTC linked is not for the issue, but since there are some missing traces, we need to enable the audio stack traces to further analyze the issue.
- 21.12.17 13:49 Manohara: test comment





## Chapter 2

# Description

The TestResultWebApp:  
TO BE CONTINUED

## Chapter 3

# Appendix

About this package:

Table 3.1: Package setup

Setup parameter	Value
Name	TestResultWebApp
Version	0.1.0
Date	04.07.2022
Description	Web based display of test results
Package URL	<a href="#">testresultwebapp</a>
Author	Thomas Pollerspöck
Email	<a href="mailto:Thomas.Pollerspoeck@de.bosch.com">Thomas.Pollerspoeck@de.bosch.com</a>
Language	Programming Language :: Python :: 3
License	License :: OSI Approved :: Apache Software License
OS	Operating System :: OS Independent
Python required	>=3.0
Development status	Development Status :: 4 - Beta
Intended audience	Intended Audience :: Developers
Topic	Topic :: Software Development

---

**CHAPTER 4. HISTORY**

---

## Chapter 4

# History

<b>0.1.0</b>	07/2022
<i>Initial version</i>	

---

**TestResultWebApp.pdf***Created at 17.08.2022 - 14:11:08**by GenPackageDoc v. 0.26.0*

---

## 3.11 TMLLog2RobotLog

**TMLLog2RobotLog**

**v. 1.1.0**

Tran Duy Ngoan

12.07.2022



# Contents

<b>1</b>	<b>Introduction</b>	<b>1</b>
<b>2</b>	<b>Description</b>	<b>2</b>
<b>3</b>	<b>__main__.py</b>	<b>3</b>
3.1	Function: process_commandline . . . . .	3
3.2	Function: TMLLog2RobotLog . . . . .	3
3.3	Class: Logger . . . . .	3
3.3.1	Method: run . . . . .	3
<b>4</b>	<b>resultbuilder.py</b>	<b>4</b>
4.1	Function: TMLExecutionResult . . . . .	4
4.2	Class: TMLExecutionResultBuilder . . . . .	4
4.2.1	Method: build . . . . .	4
<b>5</b>	<b>xmlelementhandlers.py</b>	<b>5</b>
5.1	Class: XmlElementHandler . . . . .	5
5.1.1	Method: start . . . . .	5
5.1.2	Method: end . . . . .	5
5.2	Class: _Handler . . . . .	5
5.2.1	Method: get_child_handler . . . . .	5
5.2.2	Method: start . . . . .	5
5.2.3	Method: end . . . . .	5
5.2.4	Method: to.timestamp . . . . .	5
5.2.5	Method: filename . . . . .	5
5.3	Class: UnknownHandler . . . . .	5
5.3.1	Method: get_child_handler . . . . .	5
5.4	Class: RootHandler . . . . .	5
5.5	Class: TMLHandler . . . . .	6
5.5.1	Method: start . . . . .	6
5.6	Class: MetadataSet . . . . .	6
5.6.1	Method: end . . . . .	6
5.7	Class: MetadataHandler . . . . .	6
5.8	Class: JenkinsurlHandler . . . . .	6
5.9	Class: VersionsHandler . . . . .	6
5.10	Class: VersionSWHandler . . . . .	6
5.11	Class: VersionHWHandler . . . . .	6
5.12	Class: VersionTestHandler . . . . .	6

## CONTENTS

## CONTENTS

5.13 Class: VersionTMLHandler . . . . .	6
5.14 Class: TagsHandler . . . . .	7
5.15 Class: CategoryHandler . . . . .	7
5.16 Class: QualitygateHandler . . . . .	7
5.17 Class: FileHandler . . . . .	7
5.17.1 Method: start . . . . .	7
5.18 Class: HeaderHandler . . . . .	7
5.19 Class: TeststartedHandler . . . . .	7
5.19.1 Method: end . . . . .	7
5.20 Class: TesttoolconfigurationHandler . . . . .	7
5.21 Class: TesttoolnameHandler . . . . .	7
5.21.1 Method: end . . . . .	8
5.22 Class: TesttoolversionHandler . . . . .	8
5.22.1 Method: end . . . . .	8
5.23 Class: ProjectHandler . . . . .	8
5.23.1 Method: end . . . . .	8
5.24 Class: TestfileheaderHandler . . . . .	8
5.25 Class: AuthorHandler . . . . .	8
5.26 Class: DescriptionHandler . . . . .	8
5.26.1 Method: end . . . . .	8
5.27 Class: TestexecutionHandler . . . . .	8
5.28 Class: TesterHandler . . . . .	8
5.28.1 Method: end . . . . .	8
5.29 Class: TestmachineHandler . . . . .	8
5.29.1 Method: end . . . . .	9
5.30 Class: TestrequirementsHandler . . . . .	9
5.30.1 Method: get_child_handler . . . . .	9
5.31 Class: TestbenchconfigHandler . . . . .	9
5.31.1 Method: get_child_handler . . . . .	9
5.32 Class: PreprocessorparamsHandler . . . . .	9
5.32.1 Method: get_child_handler . . . . .	9
5.33 Class: TestresultsHandler . . . . .	9
5.34 Class: TestHandler . . . . .	9
5.34.1 Method: start . . . . .	9
5.34.2 Method: end . . . . .	9
5.35 Class: ResultHandler . . . . .	9
5.36 Class: MainHandler . . . . .	9
5.36.1 Method: end . . . . .	10
5.37 Class: StateHandler . . . . .	10
5.37.1 Method: get_child_handler . . . . .	10
5.38 Class: ReturnHandler . . . . .	10
5.38.1 Method: get_child_handler . . . . .	10
5.39 Class: LastlogHandler . . . . .	10
5.39.1 Method: end . . . . .	10
5.40 Class: FooterHandler . . . . .	10
5.41 Class: TestdoneHandler . . . . .	10

<i>CONTENTS</i>	<i>CONTENTS</i>
5.41.1 Method: end . . . . .	10
<b>6 Appendix</b>	<b>11</b>
<b>7 History</b>	<b>12</b>
<hr/>	
C	

# Chapter 1

## Introduction

*TMLLog2RobotLog*  
TO BE CONTINUED

# Chapter 2

## Description

*TMLLog2RobotLog*  
TO BE CONTINUED

## Chapter 3

### \_\_main\_\_.py

#### 3.1 Function: process\_commandline

process provided argument(s) from command line Function: validate\_cli\_arguments =====

#### 3.2 Function: TMLLog2RobotLog

#### 3.3 Class: Logger

```
TMLLog2RobotLog.__main__
```

Logger class for logging message Method: config -----

Configure Logger class - output\_console: write message to console output. Default value is True - output\_logfile: path to log file output. Default is None - dryrun: if set, a prefix as 'dryrun' is added for all messages Method: log -----  
write log message to console/file output - msg: message to write to output - color: color style for the message Method: log\_warning -----

write warning message to console/file output - msg: message to write to output Method: log\_error -----

write error message to console/file output - msg: message to write to output - fatal\_error: if set, tool will terminate after logging error message Class: CTMLLog2Robot =====

```
TMLLog2RobotLog.__main__
```

CTMLLog2Robot class Method: config -----

##### 3.3.1 Method: run

process TMLLog2Robot converter Method: get\_tml\_logs -----

get TML log results Method: get\_robot\_log -----

get Robot log result Method: convert\_to\_robot -----

convert TML log results to Robot results Method: merge\_results -----

merge Robot results Method: save\_result\_file -----

save robot\_result as output\_file file Method: find\_suite -----

## Chapter 4

# resultbuilder.py

### 4.1 Function: TMLExecutionResult

### 4.2 Class: TMLExecutionResultBuilder

```
TMLog2RobotLog.resultbuilder
```

#### 4.2.1 Method: build

## Chapter 5

# xmlelementhandlers.py

### 5.1 Class: XmlElementHandler

```
TMLog2RobotLog.xml_element_handlers
```

5.1.1 Method: start

5.1.2 Method: end

### 5.2 Class: \_Handler

```
TMLog2RobotLog.xml_element_handlers
```

5.2.1 Method: get\_child\_handler

5.2.2 Method: start

5.2.3 Method: end

5.2.4 Method: to\_timestamp

5.2.5 Method: filename

### 5.3 Class: UnknownHandler

```
TMLog2RobotLog.xml_element_handlers
```

5.3.1 Method: get\_child\_handler

### 5.4 Class: RootHandler

```
TMLog2RobotLog.xml_element_handlers
```



## 5.5 Class: TMLHandler

```
TMLog2RobotLog.xml_elementhandlers
```

### 5.5.1 Method: start

## 5.6 Class: MetadataSet

```
TMLog2RobotLog.xml_elementhandlers
```

### 5.6.1 Method: end

## 5.7 Class: MetadataHandler

```
TMLog2RobotLog.xml_elementhandlers
```

## 5.8 Class: JenkinsurlHandler

```
TMLog2RobotLog.xml_elementhandlers
```

## 5.9 Class: VersionsHandler

```
TMLog2RobotLog.xml_elementhandlers
```

## 5.10 Class: VersionSWHandler

```
TMLog2RobotLog.xml_elementhandlers
```

## 5.11 Class: VersionHWHandler

```
TMLog2RobotLog.xml_elementhandlers
```

## 5.12 Class: VersionTestHandler

```
TMLog2RobotLog.xml_elementhandlers
```

## 5.13 Class: VersionTMLHandler

```
TMLog2RobotLog.xmllementhandlers
```

## 5.14 Class: TagsHandler

```
TMLog2RobotLog.xmllementhandlers
```

## 5.15 Class: CategoryHandler

```
TMLog2RobotLog.xmllementhandlers
```

## 5.16 Class: QualitygateHandler

```
TMLog2RobotLog.xmllementhandlers
```

## 5.17 Class: FileHandler

```
TMLog2RobotLog.xmllementhandlers
```

### 5.17.1 Method: start

## 5.18 Class: HeaderHandler

```
TMLog2RobotLog.xmllementhandlers
```

## 5.19 Class: TeststartedHandler

```
TMLog2RobotLog.xmllementhandlers
```

### 5.19.1 Method: end

## 5.20 Class: TesttoolconfigurationHandler

```
TMLog2RobotLog.xmllementhandlers
```

## 5.21 Class: TesttoolnameHandler

```
TMLog2RobotLog.xmllementhandlers
```

**5.21.1 Method: end**

**5.22 Class: TesttoolversionHandler**

```
TMLog2RobotLog.xml_elementhandlers
```

**5.22.1 Method: end**

**5.23 Class: ProjectHandler**

```
TMLog2RobotLog.xml_elementhandlers
```

**5.23.1 Method: end**

**5.24 Class: TestfileheaderHandler**

```
TMLog2RobotLog.xml_elementhandlers
```

**5.25 Class: AuthorHandler**

```
TMLog2RobotLog.xml_elementhandlers
```

**5.26 Class: DescriptionHandler**

```
TMLog2RobotLog.xml_elementhandlers
```

**5.26.1 Method: end**

**5.27 Class: TestexecutionHandler**

```
TMLog2RobotLog.xml_elementhandlers
```

**5.28 Class: TesterHandler**

```
TMLog2RobotLog.xml_elementhandlers
```

**5.28.1 Method: end**

**5.29 Class: TestmachineHandler**

```
TMLog2RobotLog.xml_elementhandlers
```

**5.29.1 Method: end**

**5.30 Class: TestrequirementsHandler**

```
TMLog2RobotLog.xml_elementhandlers
```

**5.30.1 Method: get\_child\_handler**

**5.31 Class: TestbenchconfigHandler**

```
TMLog2RobotLog.xml_elementhandlers
```

**5.31.1 Method: get\_child\_handler**

**5.32 Class: PreprocessorparamsHandler**

```
TMLog2RobotLog.xml_elementhandlers
```

**5.32.1 Method: get\_child\_handler**

**5.33 Class: TestresultsHandler**

```
TMLog2RobotLog.xml_elementhandlers
```

**5.34 Class: TestHandler**

```
TMLog2RobotLog.xml_elementhandlers
```

**5.34.1 Method: start**

**5.34.2 Method: end**

**5.35 Class: ResultHandler**

```
TMLog2RobotLog.xml_elementhandlers
```

**5.36 Class: MainHandler**

```
TMLog2RobotLog.xml_elementhandlers
```

**5.36.1 Method: end**

**5.37 Class: StateHandler**

```
TMLog2RobotLog.xml_elementhandlers
```

**5.37.1 Method: get\_child\_handler**

**5.38 Class: ReturnHandler**

```
TMLog2RobotLog.xml_elementhandlers
```

**5.38.1 Method: get\_child\_handler**

**5.39 Class: LastlogHandler**

```
TMLog2RobotLog.xml_elementhandlers
```

**5.39.1 Method: end**

**5.40 Class: FooterHandler**

```
TMLog2RobotLog.xml_elementhandlers
```

**5.41 Class: TestdoneHandler**

```
TMLog2RobotLog.xml_elementhandlers
```

**5.41.1 Method: end**

## Chapter 6

# Appendix

About this package:

Table 6.1: Package setup

Setup parameter	Value
Name	TMLLog2RobotLog
Version	1.1.0
Date	12.07.2022
Description	Convert TML-Framework results to Robot Framework results
Package URL	<a href="https://pypi.org/project/robotframework-tmllog2robotlog/">robotframework-tmllog2robotlog</a>
Author	Tran Duy Ngoan
Email	<a href="mailto:Ngoan.TranDuy@vn.bosch.com">Ngoan.TranDuy@vn.bosch.com</a>
Language	Programming Language :: Python :: 3
License	License :: OSI Approved :: Apache Software License
OS	Operating System :: OS Independent
Python required	>=3.0
Development status	Development Status :: 4 - Beta
Intended audience	Intended Audience :: Developers
Topic	Topic :: Software Development

## Chapter 7

# History

<b>1.0.0</b>	2022
<i>Initial version</i>	

---

**TMLLog2RobotLog.pdf***Created at 17.08.2022 - 14:11:19**by GenPackageDoc v. 0.26.0*

---

---

**RobotFrameworkAIO\_Reference.pdf***Created at 17.08.2022 - 14:09:30**by genmaindoc v. 0.14.0*

---